#### 7.2.1. CPIEM Executable File

**Cpiem.exe** instantiates CPIEM and executes all procedures for CPIEM. The file handles the overall program flow and user interface.

## 7.2.2. CPIEM Database

Key input tables within **Cpiem.mdb** are summarized for Level 1-2 in Table 7-2 and for Level 3 in Table 7-3. These tables are used to store user inputs for items such as population subgroup, concentration distributions, and indoor sources. Additional tables for Level 1-2 are used to store and match activity profiles for various integration periods. There is one table for each of the nine environments in Level 1-2. There are two tables for each of the six types of indoor sources in Level 3; two tables are needed because the inputs are relatively complex.

Although the data in many of the input tables are based directly on published data, in some instances calculations were required to convert the data to a form consistent with input requirements for CPIEM. These calculations are documented in Appendix C.

์ Table Name	Content
CL_POP	Case names and associated criteria for population subgroups
CL_BRT	Case names and associated inputs for breathing rates
CL_ENV<1 through 9>	Case names and associated inputs for concentration distributions for each of 9 micro environments: 1 for residence, 2 for office, 3 for industrial plant, 4 for school, 5 for travel in vehicle, 6 for public access building, 7 for restaurant/lounge, 8 for other indoor, or 9 for outdoors

Table 7-2 Level 1-2 Tables in CPIEM Database (Cpiem.mdb)

Note that each of the numbered tables (for example, CL\_SRC1) contains the case names and indicates the record numbers in its correspondingly numbered "D" table (for example, CL\_SRC1D), which contain the inputs for each case name.

Table Name	Content
CL_SRC1 and CL_SRC1D*	Case names and associated inputs for long-term (load factor) indoor sources
CL_SRC2 and CL_SRC2D*	Case names and associated inputs for long-term (no loading) indoor sources
CL_SRC3 and CL_SRC3D*	Case names and associated inputs for episodic (load factor) indoor sources
CL_SRC4 and CL_SRC4D*	Case names and associated inputs for episodic (no load) indoor sources
CL_SRC5 and CL_SRC5D*	Case names and associated inputs for frequent (load factor) indoor sources
CL_SRC6 and CL_SRC6D*	Case names and associated inputs for frequent (no load) indoor sources
CL_OUT1	Case names and associated inputs for daily outdoor concentrations
CL_OUT2	Case names and associated inputs for hourly outdoor concentrations
CL_PEN	Case names and associated inputs for penetration factors
CL_SNK.	Case names and associated inputs for indoor sinks
CL_VOL	Case names and associated inputs for volumes
CL_ACH	Case names and associated inputs for air exchange rates

Note: tblPollutant table stores all pollutants used in both mcdels assigns an index/id number to each pollutant. All inputs saved by users for Level 1-2 concentration distributions and Level 3 indoor sources, outdoor concentrations, penetration factors, and indoor sinks are linked to the pollutant through this index/id number.

Table 7-3 Level 3 Tables in CPIEM Database (Cpiem.mdb)

#### 7.2.3. Population Database and File

**Pop.mdb** contains information used to generate population subgroup cases. It contains input data tables for Level 1-2 Exposure/Doses integration periods.

Table Name	Content
WC_ACTAM	Input for exposure/doses for morning integration period
WC_ACTPM	Input for exposure/doses for afternoon integration period
WC_ACT1	Input for exposure/doses for 1 hour integration period
WC_ACT8	Input for exposure/doses for 8 hour integration period
WC_ACT24	Input for exposure/doses for 24 hour integration period

These files are used to determine characteristics of individuals to determine index numbers for activity profiles that match user criteria for population subgroup

#### 7.3. Output Files

Output files are the results of each scenario run and are summarized for Level 1-2 in Table 7-5 and for Level 3 in Table 7-6. The files are of two types:

- Statistical summary files (.ste & .std for Level 1-2 and \*.stc for Level3)
- Detailed (trial-by-trial) results (.prn for Level 1-2 and \*.asc for Level3)

All output files are in ASCII format. Note that if you run the same scenario more than once (for example, using different parameters) without changing the name, CPIEM will overwrite the asc. and .stc files. To save the results from a series of runs, you can either change the name of the scenario for each run, or you can manually change the names of the .asc and .stc files after they are generated.

File Name	Content
Wc_act.act	Binary file with activity profiles for individuals that match user criteria for population subgroup. This file should not be changed or deleted.
<filename>.ste</filename>	Summary statistics for exposure distributions for each environment and total across environments
<pre><filename>.std</filename></pre>	Summary statistics for dose distributions for each environment and total across environments
<filename>.pm</filename>	Detailed (trial-by-trial) results for exposure and dose for each environment and total across environments
· Ta	e 7-4 Level 1-2 Output Filos and Associate LO

Table 7-4 Level 1-2 Output Files and Associated Contents

File Name	Content
<filename>.stc</filename>	Summary statistics for hourly-average and daily-average concentrations
<filename>.asc</filename>	Detailed (trial-by-trial) results for hourly-average and daily-average concentrations

<sup>\*</sup> in which <filename> is the six character file name that CPIEM automatically assigns using the first 6 character of the associated scenario name.

**Table 7-5 Level 3 Output Files and Associated Contents** 

#### **Specifying an Output Directory** 7.4.

To better manage the output files are scenario runs, CPIEM provides an option for creating user specified output folders. This option can be exercised by selecting Options from the Help menu, and typing a folder name in the Output Folder field. Any existing directory or subdirectory may be specified. CPIEM will prompt the user if the folder does not already exist before creating a new one. NOTE: In order for a folder to be created under the root CPIEM directory, it may only be a single level of folder, i.e. "...\Cpiem\(folder1)" and not multiple levels such as "...\Cpiem\ (folder1)\(folder2) ". Otherwise, an error condition will be indicated, as follows.



## 7.5. Creating a Data Set files

Although most inputs to the model are in the form of parameters that describe distributions (e.g., normal, lognormal), data sets can also be provided for concentration inputs. A data set used by the model must be in a prescribed format. The Dataset.dbf (dBase III) file provides this format. Use this file as template when creating data set files. Several dataset files are also included in the installation set that can be used as examples.

When creating a .dbf file, it is recommended that data be added to a copy of the empty Dataset.dbf file, rather than editing a .dbf file containing data. To edit a copy of the given Dataset.dbf file(s), several different options are available that can be used based on user's preference and familiarity. The recommended tools are using a dBase file utility (e.g. dbMax), Access 9x or 2000 where the dbf file can be edited as an attached file, or earlier versions of Excel (e.g., 95), in the order listed.

## 7.6. Choosing a Random Number Generator Scheme

CPIEM 2.0 provides two schemes for generating random numbers, option A (default) and option B (for backward compatibility with the DOS version). See section 2.3.7 for more details.

This page intentionally left blank.

# Appendix A: Hardware Requirements and Software Installation

## **System Requirements**

CPIEM has been designed to run with the following hardware and platform:

- Computer with Pentium microprocessor or higher.
- Hard disk with available capacity of 50 Mb or greater.
- VGA monitor or better.
- Microsoft Windows 95 or higher (98, NT, 2000)
   (CPIEM has not been installed or tested on Windows XP, but it should work as well on this new platform)
- Users who will be updating the database files will need Microsoft Access 97.

## **Installing CPIEM**

The installation package on CD contains **CPIEM.CAB**, **SETUP.EXE**, and **SETUP.LST**. To install CPIEM:

- 1. Close all active computer programs or applications, except for Windows itself.
- 2. Double-click on Setup.exe.
- 3. CPIEM will open the CPIEM 2.0 Setup installation program. Follow the instructions given to install CPIEM.
- 4. Select the default directory "C:\Program Files\CPIEM" to install into, and click OK.
- 5. When you have finished making your selections, CPIEM will notify you that installation has been completed.

See Section 7 in the main document for a list and description of the installed files.

IMPORTANT NOTE: Re-installing CPIEM would also install fresh copies of all application databases and data files that will over-write the existing CPIEM data. To preserve your data between installations, you would need to backup all files under "...\CPIEM\Data" directory by copying them to a different location. It is a good practice to archive your data periodically in any case. Once the re-installation is complete, you can copy the data back to this directory. A complete list of these data files is included in section 7.

## **Uninstalling CPIEM**

To uninstall CPIEM, follow the same process as removing any other 32-bit windows application:

- 1. From the Start menu, open the Control Panel and Double-click on "Add/Remove Programs."
- 2. Select CPIEM application in the dialogue box and Click "Remove."

## Re-installing CPIEM

If you are re-installing an upgrade version of CPIEM, you would need to un-install the application as described above prior to re-installing the new version.

## Appendix B: Input Data Provided with the Model

### **Level 1-2 Inputs**

Inputs provided for Level 1-2 of the model describe concentration distributions for five types of environments—residence, office, school, travel in vehicle, and outdoors. Four other types of environments in the model—industrial plant, public access building, restaurant/lounge, and other indoor—currently have no inputs. The pollutants and integration periods for which input data are available are summarized in Table B-1. Some data are available for all pollutants in the model except total PAHs. The greatest amount of data is available for residences, followed by outdoors and travel in vehicle.

The concentration inputs for each type of environment are listed in Table B-2 for residences, B-4 for offices, B-5 for schools, B-6 for travel in vehicle, and B-7 for outdoors. Each listing indicates the case name by which the data are accessed in the model together with the pollutant, averaging period, and distribution type. Distributions for which data are provided are of four types: (1) normal, for which the arithmetic mean concentration and arithmetic standard deviation are listed (2) lognormal, for which the arithmetic mean concentration and arithmetic standard deviation are listed, (3) percentile, for which various percentiles of the cumulative frequency distribution are listed together with associated concentration values, and (4) data sets, for which the specific values are listed. Table B-3 provides recommended weights for the default cases for residences.

Table B-1 Summary of Concentration Data Available for Model Level 1-2

Pollutant	Residence (Envir 1)	Office (Envir 2)	School (Envir 4)	Travel in Vehicle (Envir 5)	Outdoors (Envir 9)
Benzene	24,A,P*	Α	1	24,A,P	24,A,P
Benzo(a)pyrene	24,A,P	Α	<u> </u>	1	24,A,P
Carbon	24			1,24	24
Monoxide	24,A,P			24,A,P	24,A,P
Chloroform	24	24,A		1, 24	24
Formaldehyde	24			1	24,A,P
Nitrogen Dioxide	24,A,P	Α		1	24,A,P
PM10	24,A,P		1	24,A,P	24
Perchlorethylene					
Total PAHs	24,A,P	Α	1		24,A,P
Trichloroethylene	24				
Ozone				1	
MTBE				1	
1,3-Butadiene				•	

<sup>\* 24</sup> refers to a 24-hour integration period, A refers to a 12-hour daytime period, and P refers to a 12-hour nighttime period.

Table B-2 Concentration Distributions for Residences (Level 1-2)

Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type for Data
3	WOODSL <sup>a</sup>	1	Benzene	24	Lognormal(4.50,10.24)
4	WOODSP	1	Benzene	24	Percentile(0,0; 10,0.84; 25,1.50; 50,2.20; 75,4.80;
5	TM87B24L	2	Benzene	24	90,9.40; 100,130.00)
6	TM87B24P	2	Benzene	24	Lognormal(8.95,10.44)  Percentile(0,1.47; 5,1.64; 10,2.08; 25,3.41; 50,5.84; 75,9.84; 90,16.10; 95,31.70; 100,68.60)
	TM87W24L <sup>a</sup>	2	Benzene	24	Lognormal(12.12,12.98)
8	TM87W24P	2	Benzene	24	Percentile(0,1.47; 5,1.72; 10,2.20; 25,4.56; 50,9.00; 75,14.25; 90,26.19; 95,48.56; 100,68.60)
9 10	TM87S24L <sup>a</sup>	2	Benzene	24	Lognormal(5.95,6.10)
	TM87S24P	2	Benzene	24	Percentile(0,1.51; 5,1.55; 10,1.76; 25,2.72; 50,4.58; 75,7.56; 90,9.37; 95,20.93; 100,36.03)
11	TM87BDYL <sup>a</sup>	2	Bénzene	AM	7
12	TM87WDYL	2	Benzene	AM	Lognormal(8.23,11.84)
13	TM87SDYL	2	Benzene	AM	Lognormal(10.97,15.70)
14	TM87BNTL <sup>a</sup>	2	Benzene	PM	Lognormal(5.50,4.73)
15	TM87WNTL	2	Benzene	PM	Lognormal(10.49,11.46)
16	TM87SNTL	2	Benzene	PM	Lognormal(14.56,13.31)
17	TM84LAWL <sup>a</sup>	3	Benzene	PM	Lognormal(6.54,7.61)
18	TM84LASL <sup>a</sup>	3	Benzene	PM	Lognormal(16.50,13.80)
19	TM84CCSL <sup>a</sup>	3	Benzene	PM	Lognormal(7.78,9.26)
20	PTM24L	4	Benzo(a)Pyrene	24	Lognormal(6.47,8.31) Lognormal(.70,4.00)
21	PTMDYL	4	Benzo(a)Pyrene	AM	Lognormal(.70,4.00)
22	PTMNTL	4	Benzo(a)Pyrene	PM	Lognormal(.77,4.76)
23	WOODSP <sup>a</sup>	1	Chloroform	24	Percentile(0,0; 10,0; 25,0.20; 50,0.40; 75,1.20; 90,2.70; 100,4.00)
24	TM87B24L	2	Chloroform	24	Lognormal(1.31,1.58)
25	TM87B24P	2	Chloroform	24	Percentile(0,0.07; 5,0.07; 10,0.08; 25,0.34; 50,0.76; 75,1.70; 90,2.99; 95,5.44; 100,7.79)
26	TM87W24L <sup>a</sup>	2	Chloroform	24	
27	TM87W24P	2	Chloroform	24	Lognormal(1.41,1.52) Percentile(0,0.07; 5,0.08; 10,0.11; 25,0.34; 50,0.97; 75,1.79; 90,3.64; 95,5.10; 100,7.23)
28	TM87S24L <sup>a</sup>	2	Chloroform	24	100,7.23) Lognormal(1.20,1.65)

Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type for Data
29	TM87S24P	2	Chloroform	24	Percentile(0,0.07; 5,0.07; 10,0.07; 25,0.34; 50,0.65; 75,1.28; 90,2.47; 95,6.75; 100,7.79)
30	TM87BDYL <sup>a</sup>	2	Chloroform	AM	Lognormal(1.27,1.45)
31	TM87WDYL	2	Chloroform	AM	Lognormal(1.38,1.48)
32	TM87SDYL	2	Chloroform	AM .	Lognormal(1.13,1.41)
33	TM87BNTL <sup>a</sup>	2	Chloroform	PM	Lognormal(1.43,2.33)
34	TM87WNTL	2	Chloroform	PM	Lognormal(1.46,2.04)
35 .	TM87SNTL	2	Chloroform	PM	Lognormal(1.39,2.64)
36	TM84LAWL <sup>a</sup>	3	Chloroform	PM	Lognormal(2.17,2.01)
37	TM84LASL <sup>a</sup>	3	Chloroform	PM	Lognormal(1.57,3.39)
38	TM84CCSL <sup>a</sup>	3	Chloroform	PM	Lognormal(.80,1.58)
39	SEXMOBSL <sup>b</sup>	5a	Formaldehyde	24	Lognormal(111.70,84.70)
40	SEXMOBSPb	5a	Formaldehyde	24	Percentile(0,6.14; 6,30.70; 30,61.40; 53,92.00; 69,122.70; 84,184.10; 91,245.40; 96,368.10; 100,569.30)
41	SEXMOBWLb	5a	Formaldehyde	24	Lognormal(111.70,63.80)
42	SEXMOBWPb	5a	Formaldehyde	24	Percentile(0,20.90; 1,30.70; 20,61.40; 44,92.00; 69,122.70;
•			78		89,184.10; 96,245.40; 99,368.10; 100,385.30)
43	SEXCONWL	5b	Formaldehyde	24	Lognormal(46.60,20.90)
44	SEXCONWP <sup>b</sup>	5b	Formaldehyde	24	Percentile(0,16.00; 10,24.50; 44,36.80; 57,49.10; 77,61.40; 91,73.60; 93,85.90; 99,98.20; 100,104.30)
45	ROGCONL⁵	6	Formaldehyde	24	Lognormal(61.10,25.80)
46	ROGCONP⁵	6	Formaldehyde	24	Percentile(0,22.10; 3,24.50; 13,36.80; 36,49.10; 63,61.40; 77,73.60; 86,85.90; 91,98.20; 94,110.40; 97,122.70; 100,147.20)
47	HARVLALC	7	Nitrogen Dioxide	24	Lognormal(51.20,30.40)
48	HARVLAP°	7	Nitrogen Dioxide	24	Percentile(0,6.60; 5,13.40; 10,18.70; 25,31.30; 50,46.40; 75,65.80; 90,84.30; 95,100.90; 99,167.80; 100,289.40)
49	SOCLJNKL	8	Nitrogen Dioxide	24	Lognormal(114.60,67.20)

Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type for Data
50	SOCLJNKPb	8	Nitrogen Dioxide	24	Percentile(0,3.00; 5,34.50; 10,43.60; 25,65.20; 50,100.70; 75,147.90; 90,212.90; 95,244.70; 99,325.90; 100,390.80)
51	SOCLJNBL⁵	8	Nitrogen Dioxide	24	Lognormal(82.30,53.10)
52	SOCLJNBP <sup>b</sup>	8	Nitrogen Dioxide	24	Percentile(0,1.60; 5,23.30; 10,31.00; 25,47.80; 50,70.40; 75,104.50; 90,138.40; 95,168.60; 99,312.40; 100,390.80)
53	SOCLMRKL	8	Nitrogen Dioxide	24	Lognormal(81.10,48.70)
54	SOCLMRKP <sup>b</sup>	8	Nitrogen Dioxide	24	Percentile(0,0; 5,21.00; 10,26.00; 25,40.00; 50,73.00; 75,110.00; 90,146.00; 95,167.00; 99,223.00; 100,330.00)
55	SOCLMRBL®	8	Nitrogen Dioxide	24	Lognormal(55.70,34.40)
56	SOCLMRBP⁵	8	Nitrogen Dioxide	24	Percentile(0,0; 5,15.00; 10,21.00; 25,31.00; 50,48.50; 75,72.00; 90,97.00; 95,121.00; 99,170.00; 100,247.00)
57	SOCLJLKL <sup>b</sup>	3	Nitrogen Dioxide	24	Lognormal(93.40,46.30)
58	SOCLJLKP⁵	8	Nitrogen Dioxide	24	Percentile(0,0.40; 5,26.90; 10,38.00; 25,60.80; 50,88.80; 75,122.60; 90,152.90; 95,171.20; 99,210.70; 100,260.60)
59	SOCLJLBL⁵	8	Nitrogen Dioxide	24	Lognormal(71.60,33.70)
60	SOCLJLBP⁵	8	Nitrogen Dioxide	24	Percentile(0,0.60; 5,23.30; 10,30.60; 25,47.30; 50,69.20; 75,91.80; 90,114.10; 95,127.50; 99,159.00; 100,203.00)
61	PTEAMFL <sup>a</sup>	4	Inhalable Particles (PM10)	24	Lognormal(79.00,51.40)
62	PTEAMFP	4	Inhalable Particles (PM10)	24	Percentile(0,19.90; 10,32.90; 25,45.10; 50,65.30; 75,106.40; 90,143.60; 100,324.80)
63	COLOMFL	9	Inhalable Particles (PM10)	24	Lognormal(42.50,21.90)
64	PTEAMFL <sup>a</sup>	4	Inhalable Particles (PM10)	AM	Lognormal(94.70,74.10)
65	PTEAMFL <sup>a</sup>	4	Inhalable Particles (PM10)	PM	Lognormal(62.70,40.90)
66	WOODSL <sup>a</sup>	1	Perchloroethylene	24	Lognormal(1.44,6.12)

Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type for Data
67	WOODSP	1	Perchloroethylene	24	Percentile(0,0; 10,0; 25,0.12; 50,0.24; 75,0.73; 90,2.30; 100,30.00)
68	TM87B24L	2	Perchioroethylene	24	Lognormal(4.93,6.20)
69	TM87B24P	2	Perchloroethylene	24	Percentile(0,0.60; 5,0.69; 10,1.46; 25,2.24; 50,3.12; 75,4.95; 90,8.20; 95,17.67; 100,44.22)
70	TM87W24L <sup>a</sup>	2	Perchloroethylene	24	Lognormal(6.74,7.66)
71 72	TM87W24P	2	Perchloroethylene	24	Percentile(0,0.66; 5,1.19; 10,2.09; 25,2.99; 50,4.42; 75,7.12; 90,17.27; 95,21.90; 100,44.22)
73	TM87S24L <sup>a</sup>	2	Perchloroethylene	24	Lognormal(2.46,1.10)
	TM87S24P	2	Perchloroethylene	24	Percentile(0,0.60; 5,0.62; 10,0.74; 25,1.84; 50,2.48; 75,2.88; 90,4.57; 95,4.71; 100,4.78)
74	TM87BDYL <sup>a</sup>	2	Perchloroethylene	AM	Lognormal(4.56,6.28)
75	TM87WDYL	2	Perchloroethylene	AM	Lognormal(5.86,7.96)
76	TM87SDYL	2	Perchloroethylene	AM	Lognormal(2.80,1.68)
77	TM87BNTL <sup>a</sup>	2	Perchloroethylene	PM	Lognormal(5.03,6.52)
78	TM87WNTL	2	Perchloroethylene	PM	Lognormal(7.71,7.72)
79	TM87SNTL	2	Perchloroethylene	PM	Lognormal(1.70,1.30)
80	TM84LAWL <sup>a</sup>	3	Perchloroethylene	PM:	Lognormal(13.50,17.40)
81	TM84LASL <sup>a</sup>	3	Perchloroethylene	PM	Lognormal(3.99,11.20)
82	TM84CCSL <sup>a</sup>	3	Perchloroethylene	PM	Lognormal(3.36,5.57)
83	WOODSL <sup>a</sup>	1 1	Trichloroethylene	24	Lognormal(.65,1.57)
84	WOODSP	1	Trichloroethylene	24	Percentile(0,0; 10,0; 25,0.09; 50,0.19; 75,0.56; 90,1.90; 100,9.30)
85	TM87B24L	2	Trichloroethylene	24	Lognormal(1.01,1.49)
86	TM87B24P	2	Trichloroethylene	24	Percentile(0,0.06; 5,0.08; 10,0.16; 25,0.18; 50,0.39; 75,1.08; 90,3.38; 95,4.75; 100,7.27)
87	TM87W24L <sup>a</sup>	2	Trichloroethylene	24	Lognormal(.93,1.20)
88	TM87W24P	2	Trichloroethylene	24	Percentile(0,0.06; 5,0.06; 10,0.15; 25,0.18; 50,0.47; 75,1.24; 90,2.25; 95,4.60; 100,5.02)
89	TM87S24L <sup>a</sup>	2	Trichloroethylene	24	Lognormal(1.10,1.77)
90	TM87S24P	2	Trichloroethylene	24	Percentile(0,0.06; 5,0.13; 10,0.16; 25,0.18; 50,0.34; 75,0.90; 90,4.21; 95,6.55; 100,7.27)
91	TM87BDYL <sup>a</sup>	2	Trichloroethylene	AM	Lognormal(.87,1.31)
92	TM87WDYL	2	Trichloroethylene		Lognormal(.99,1.35)
93	TM87SDYL	2	Trichloroethylene	AM	Lognormal(.72,1.27)

Case	Casa Name			Averaging	Distribution Type
Number	Case Name	Ref	Pollutant	Period	for Data
94	TM87BNTL <sup>a</sup>	2	Trichloroethylene	PM	Lognormal(1.37,2.65)
95	TM87WNTL	2	Trichloroethylene	PM	Lognormal(1.38,2.55)
96	TM87SNTL	2	Trichloroethylene	PM	Lognormal(1.35,2.80)
97	TM84LAWL <sup>a</sup>	3	Trichloroethylene	PM	Lognormal(3.97,8.15)
98	TM84LASL <sup>a</sup>	3	Trichloroethylene	PM	Lognormal(2.02,7.64)
99	TM84CCSL <sup>a</sup>	3	Trichloroethylene	PM	Lognormal(.76,1.00)
100	CRIAQALL°	10	Benzene	24	Lognormal(10.86,7.99)
101	CRIAQPGL°	10	Benzene	24	Lognormal(8.63,5.43)
102	CRIAQSCL°	10	Benzene	24	Lognormal(15.66,8.95)
103	CRIAQSDL°	10	Benzene	24	Lognormal(8.63,8.95)
104	CRIAQALL°	10	Nitrogen Dioxide	24	Lognormal(47.00,50.80)
105	CRIAQALP°	10	Nitrogen Dioxide	24	Percentile(0,0; 5,3.80; 25,16.90; 50,30.10; 75,60.20; 95,139.20; 100,332.90)
106	CRIAQPGL <sup>c</sup>	10	Nitrogen Dioxide	24	Lognormal(35.70,48.90)
107	CRIAQPGP°	10	Nitrogen Dioxide	24	Percentile(0,0; 5,0; 25,11.29; 50,20.69; 75,43.26; 95,142.96; 100,312.25)
108	CRIAQSCL°	10	Nitrogen Dioxide	24	Lognormal(64.00,58.30)
109	CRIAQSCP°	10	Nitrogen Dioxide	24	Percentile(0,0; 5,3.80; 25,28.20; 50,54.60; 75,82.80; 95,159.90; 100,332.90)
110	CRIAQSDL°	10	Nitrogen Dioxide	24	Lognormal(47.00,39.50)
111	CRIAQSDP°	10	Nitrogen Dioxide	24	Percentile(0,7.50; 5,11.30; 25,22.60; 50,30.10; 75,64.00; 95,118.50; 100,212.60)
112	CRIAQALL°	10	Carbon Monoxide	24	Lognormal(1.80,1.90)
113	CRIAQALP <sup>c</sup>	10	Carbon Monoxide	24	Percentile(0,0; 5,0.10; 25,0.80; 50,1.40; 75,2.10; 95,4.90; 100,14.80)
114	CRIAQPGL°	10	Carbon Monoxide	24	Lognormal(1.50,1.60)
115	CRIAQPGP°	10	Carbon Monoxide	24	Percentile(0,0; 5,0.10; 25,0.70; 50,1.00; 75,1.60; 95,3.80; 100,13.60)
116	CRIAQSCL <sup>c</sup>	10	Carbon Monoxide	24	Lognormal(3.10,2.70)
117	CRIAQSCP°	10	Carbon Monoxide	24	Percentile(0,0.30; 5,0.70; 25,1.40; 50,2.10; 75,3.70; 95,8.40; 100,14.80)
118	CRIAQSDL°	10	Carbon Monoxide	24	Lognormal(1.30,.90)
119	CRIAQSDP°	10	Carbon Monoxide	24	Percentile(0,0.10; 5,0.20; 25,0.70; 50,1.30; 75,1.60; 95,3.20; 100,4.90)
					(continued)

Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type for Data
120	AVOLLA	22	Ozone	24	Percentile (1,0.0, 5, 0.0, 10, 0.0, 25, 3.93, 50, 11.78, 75, 31.41, 90, 62.82, 95, 82.45, 99, 98.16)
121	COLOCA	23	Benzene	24	Percentile (1, 1.6, 5, 2.23, 25, 3.83, 50, 6.7, 75, 10.53, 95, 24.25, 100, 35.73)
122	COLOPGE°	23	Benzene	24	Percentile (1, 1.6, 5, 2.23, 25, 3.51, 50, 5.74, 75, 8.93, 95, 14.99, 100, 35.73)
123	COLOSD°	23	Benzene	24	Percentile(1, 1.91, 5, 3.19, 25, 3.83, 50, 5.42, 75, 8.29, 95, 14.67, 100, 33.5)
124	OFFECAAM	24	Benzo(a)pyrene	AM .	Dataset (0.038, 0.036, 0.60, 0.13, 6.6)
125	PETEOZ	25	Ozone	24	Normal (25.52, 23.56)
126	PETEPM	25	PM10	24	Normal (40.6, 36.6)
127	PETEFM	25	Formaldehyde	24	Normal (11.3, 7.4)
128	OFFECAPM	24	Benzo(a)pyrene	PM	Dataset(0.018, 0.018, 0.20, 0.045, 0.20)
129	COLOSC°	23	Benzene	24	Percentile(1, 1.91, 5, 2.55, 25, 8.29, 50, 11.17, 75, 18.18, 95, 29.03, 100, 35.09)

- a Indicates case marked as default; see Table B-3 for recommended weights for default cases.
- b Data for these cases are based on week-long measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.
- c Data for these cases are based on 48-hour measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.

Table B-3 Recommended Weights (in Percents) for Default Cases for Residences

	24-Hour		Daytime		Nighttin	ne
	Case Name (#)	Weight	Case Name (#)	Weight	Case Name (#)	Weight
Benzene	WOODSL (3)	34	TM87BDYL (11)	100	TM87BNTL (14)	70 .
	TM87W24L (7)	33			TM84LAWL (17)	10
	TM87S24L (9)	33			TM84LASL (18)	10
					TM84CCSL (19)	10
Benzo(a)pyrene	PTM24L (20)	100	PTMDYL (21)	100	PTMNTL (22)	100
Carbon Monoxide	CRIAQALL (112)	100				
Chloroform	WOODSP (23)	34	TM87BDYL (30)	100	TM87BNTL (33)	70
	TM87W24L (26)	33			TM84LAWL (36)	10
	TM87S24L (28)	33			TM84LASL (37)	10
The street street and the street stre					TM84CCSL (38)	10
Formaldehyde	SEXMOBSL (39)	100				
Nitrogen Dioxide	HARVLAL (47)	100	eteller til til hande til kall fråde og ette for ette fråde fråde fråde fråde fråde fråde fråde fråde fråde fr	anti-ori ang manga tagik sa ng		
PM10	PTEAMFL (61)	100	PTEAMFL (64)	100	PTEAMFL (65)	100
Perchloroethylene	WOODSL (66)	34	TM87BDYL (74)	100	TM87BNTL (77)	70
	TM87W24L (70)	33			TM84LAWL (80)	10
	TM87S24L (72)	33			TM84LASL (81)	10
**************************************				ŀ	TM84CCSL (82)	10
Trichloroethylene	WOODSL (83)	34	TM87BDYL (91)		TM87BNTL (94)	70
	TM87W24L (87)	33			TM84LAWL (97)	10
	TM87S24L (89)	33			TM84LASL (98)	10
					TM84CCSL (99)	10

Table B-4 Concentration Distributions for Offices (Level 1-2)

	Offices										
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type						
10	WOMBFM <sup>a,c</sup>	27	Formaldehyde	AM	Dataset (9.3, 1, 5.6, 7.9, 6.8, 16, 23, 19, 7.3, 8.5, 8.3, 12, 15, 17, 8.5, 6.1, 8.4, 3.9, 4.4, 5.4, 3.1, 3.3, 3.8, 8.4, 9.3 10,5.2, 5.7, 5.3,17, 21, 21, 8.4, 12, 8.5 21, 29, 27, 9.2, 11,11, 13, 13, 14, 15, 16, 15)						
4	ROGOL <sup>b</sup>	6	Formaldehyde	24	Lognormal (41.20,15.60)						
, 5 g	TURKL	11.	Formaldehyde	- <b>24</b>	Lognormal (28.20,12.40)						
6	DAISBEN°	26	Benzene	AM	Lognormal (1.6, 2.08)						
. 7	DAISTRIC	26	Trichloroethylene	AM	Lognormal (2.46, 2.28)						
8	OFFEBAP	24	Benzo(a)pyrene	AM	Dataset (0.044, 0.38)						
9	WOMBPM <sup>a,c</sup>	27	PM10		Dataset (13, 4.7,6.2,11, 12, 19, 11, 15, 18, 11, 15, 18, 11,11,12, 8.5,12, 9.6, 12,13, 13, 13, 11, 12, 6, 6.9, 7.1, 9.1, 6.7, 7.4, 8, 9, 12, 31, 5.3, 7.4, 9.3, 13, 24, 29, 16, 14, 16, 15, 15, 12)						

- a Indicates case marked as default. See Table B-4a for recommended weights for default cases.
- b Data for these cases are based on biweekly measurements. Although they are included among model inputs for the 24-hour averaging period, they are not recommended for use as model inputs for the 24-hour averaging period. Any modeling results using this data should be interpreted with caution.
- c Data for these cases are based on 8-hour daytime average measurements, but are appropriate for use as model inputs for the AM (12-hour daytime) averaging period in the office environment.

Table B-4a Recommended Weights (in Percents) for Default Cases for Offices

	24-Hour		Day Time			
	Case Name (#)	Weight	Case Name (#)	Weight		
Formaldehyde	WOMBFM(10)	100	WOMBFM(10)	100		
PM10	WOMBPM(9)	100	WOMBPM(9)	100		

**Table B-5 Concentration Distributions for Schools (Level 1-2)** 

	Schools									
Case Number	Case Name	ase Name Ref Pol		Averaging Period	Distribution Type					
4	UNDEBEN a,b 28 Benzene		Benzene		Dataset (3.19, 4.79, 8.93, 12.12, 2.55, 3.83, 9.57, 9.57, 1.6, 1.91, 4.79, 4.79, 3.83, 4.79, 2.87)					
5	UNDETET a,b	28	Perchlorethylene		Dataset (0.34, 0.41, 0.81, 0.81, 0.61, 0.68, 0.81, 0.88, 0.68, 0.75, 0.81, 1.02, 1.49, 2.99, 3.12)					
6	UNDETRI a,b	28	Trichloroethylene		Dataset (1.94, 1.61, 2.31, 2.53, 15.01, 14.15, 12.85, 12.59)					

(California Portable Classrooms Study data will be available in 2003)

<sup>&</sup>lt;sup>a</sup> There are no appropriate default data available for schools. Data from the California Portable Classrooms Study will be available in 2003.

<sup>&</sup>lt;sup>b</sup> Data for these cases are based on 30-minute average measurements. Although they are included among model inputs for the 1-hour averaging period, they are of limited use as model inputs for the 1-hour averaging period. Any modeling results using this data should be interpreted with caution.

Table B-6 Concentration Distributions for Travel in Vehicle (Level 1-2)

	Travel in Vehicle								
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type				
18	RODEBUTAª	29	1,3-Butadiene	1	Dataset – see Appendix H in reference 29				
19	RODEMTBE	29	MTBE	1	Dataset – see Appendix H in reference 29				
20	RODEFORMa	29	Formaldehyde	1	Dataset – see Appendix H in reference 29				
21	RODEPM10 <sup>a</sup>	29	PM10	1	Dataset – see Appendix H in reference 29				
22	RODECO <sup>a</sup>	29	Carbon Monoxide	1	Dataset – see Appendix H in reference 29				
25	RODEBENZ <sup>a</sup>	29	Benzene	1	Dataset – see Appendix H in reference 29				
26	RODEBUTA <sup>a</sup>	29	1,3-Butadiene	24	Dataset – see Appendix H in reference 29				
27	RODEMTBE	29	МТВЕ	24	Dataset – see Appendix H in reference 29				
28	RODEFORM®	29	Formaldehyde	24	Dataset – see Appendix H in reference 29				
28	RODEPM10 <sup>a</sup>	29	PM10	24	Dataset – see Appendix H in reference 29				
30	RODECO <sup>a</sup>	29	Carbon Monoxide	24	Dataset – see Appendix H in reference 29				
31	RODEBENZ <sup>a</sup>	29	Benzene	24	Dataset – see Appendix H in reference 29				
3	SHIKL <sup>b</sup>	12	Benzene	24	Lognormal (42.50,30.70)				
4	SHIKL <sup>b</sup>	12	Benzene	AM	Lognormal (42.50,30.70)				
5	SHIKL <sup>b</sup>	12	Benzene	РМ	Lognormal (42.50,30.70)				
6	SHIKL <sup>b</sup>	12	Chloroform	24	Lognormal (0.44,0.15)				
7	SHIKL <sup>b</sup>	12	Chloroform	AM	Lognormal (0.44,0.15)				
8	SHIKL <sup>b</sup>	12	Chloroform	PM	Lognormal (0.44,0.15)				
9	SHIKL <sup>b</sup>	12	Formaldehyde	24	Lognormal (15.30,6.40)				
10	SHIKL <sup>b</sup>	12	Perchloroethylene	24	Lognormal (37.30,32.60)				
11	SHIKL <sup>b</sup>	12	Perchloroethylene	AM	Lognormal (37.30,32.60)				
12	SHIKL <sup>b</sup>	12	Perchloroethylene	РМ	Lognormal (37.30,32.60)				
14	SHIKL <sup>b</sup>	12	Carbon monoxide	24	Lognormal (9.90,5.70)				

<sup>&</sup>lt;sup>a</sup> Defaults based on measurements in Los Angeles and Sacramento. See Table B-6a for recommended weights for default cases.

<sup>&</sup>lt;sup>b</sup> Los Angeles data from 1987. Concentrations are high compared to 1997 study of Rodes et al, due to changes in emissions and roadways over time.

Table B-6a Recommended Weights (in Percents) for Default Cases for Travel in Vehicle

	1-Hour		24-Hour		
	Case Name (#)	Weight	Case Name (#)	Weight	
Carbon Monoxide	RODECO (22)	100	RODECO (30)	100	
Formaldehyde	RODEFORM (20)	100	RODEFORM (28)	100	
PM10	RODEPM10 (21)	et a de la companya d	RODEPM10 (29)	100	
1,3 Butadiene	RODEBUTA (18)	100	RODEBUTA (26)	100	
MTBE	RODEMTBE (19)	100	RODEMTBE (27)	160	
Benzene	RODEBENZ (25)	100	RODEBENZ (31)	100	

Table B-7 Concentration Distributions for Outdoors (1-2)

			Outdoors		
Case Number	Case Name	Ref		Averaging Period	Distribution Type (Data)
3	TXNETALL	13	Benzene	24	Lognormal (8.04,6.78)
4	TXNETSCL	13	Benzene	24	Lognormal (10.20,7.07)
5	TXNETSFL	13	Benzene	24	Lognormal (7.27,6.48)
6	TXNETRSL	13	Benzene	24	Lognormal (7.46,5.83)
7	WOODOUTL	1	Benzene	24	Lognormal (1.20,0.62)
8	TM87B24L	2	Benzene	24	Lognormal (5.10,3.46)
9	TM87W24L	2	Benzene	24	Lognormal (6.41,3.83)
10	TM87S24L	2	Benzene	24	Lognormal (3.75,2.41)
11	TM84LAWL	3	Benzene	РМ	Lognormal (18.90,9.11)
12	TM84LASL	3	Benzene	PM	Lognormal (3.07,2.16)
13	TM84CCSL	3	Benzene	PM	Lognormal (1.82,1.01)
14	TM87BDYL	2	Benzene	AM	Lognormal (4.10,2.81)
15	PTM24L	4	Benzo(a)Pyrene	24	Lognormal (0.30,0.36)
16	PTMDYLa	4	Benzo(a)Pyrene	AM	Lognormal (0.17,0.26)
17	PTMNTL <sup>a</sup>	4	Benzo(a)Pyrene	PM	Lognormal (0.44,0.51)
18	TXNETALL	13	Chloroform	24	Lognormal (0.19,0.59)
19	TXNETSCL	13	Chloroform	24	Lognormal (0.18,0.16)
20	TXNETSFL	13	Chloroform	24	Lognormal (0.17, 0.14)
21	TXNETRSL	13	Chloroform	24	Lognormal (0.21,0.86)
22	TM87B24L	2	Chloroform	24	Lognormal (0.64,1.11)
23	TM87W24L	2	Chloroform	24	Lognormal (0.49,0.80)
24	TM87S24L	2	Chloroform	24	Lognormal (0.79,1.36)
25	TM84LAWL	3	Chloroform	PM	Lognormal (1.14,1.86)
26	TM84LASL	3	Chloroform	РМ	Lognormal (0.35,0.58)
27	TM84CCSL	3	Chloroform	PM	Lognormal (0.59,0.47)
28	TXNETALL	13	Benzo(a)Pyrene	24	Lognormal (0.84,1.87)
29	TXNETSCL	13	Benzo(a)Pyrene	24	Lognormal (0.42,0.74)
30	TXNETSFL	13	Benzo(a)Pyrene	24	Lognormal (0.54,0.88)
31	TXNETRSL		Benzo(a)Pyrene	24	Lognormal (1.03,2.02)
32	TOXALL		Formaldehyde	24	Lognormal (4.00,3.20)
33	TOXSCL		Formaldehyde	24	Lognormal (4.60,3.70)
34	TOXSFL		Formaldehyde	24	Lognormal (3.20,2.40)
35	TOXRSL	13	Formaldehyde	24	Lognormal (3.60,2.70)
36	HARVLAL <sup>a,c</sup>		Nitrogen Dioxide	24	Lognormal (72.00,39.30)
37	SOCLJANL		Nitrogen Dioxide	24	Lognormal (107.00,42.50)
38	SOCLMARL		Nitrogen Dioxide	24	Lognormal (53.70,22.60)
39	SOCLJULL		Nitrogen Dioxide	24	Lognormal (77.20,34.20)
40	TXNETALL		Inhalable Particles (PM10)	24	Lognormal (38.60,34.60)
41	TXNETSCL		Inhalable Particles (PM10)	24	Lognormal (51.60,37.20)
42	TXNETSFL		Inhalable Particles (PM10)		Lognormal (30.70,24.80)
43	TXNETRSL		Inhalable Particles (PM10)	24	Lognormal (37.00,34.90)
44	PTEAMFL <sup>a</sup>		Inhalable Particles (PM10)	24	Lognormal (91.20,50.70)
45	PTEAMFL <sup>a</sup>		Inhalable Particles (PM10)		Lognormal (94.90,70.60)
46	PTEAMFL <sup>a</sup>		Inhalable Particles (PM10)		Lognormal (86.30,56.00)
47	TXNETALL	13 I	Perchloroethylene		Lognormal (2.18,3.89)
					(continued)

•			Outdoors		
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type (Data)
48	TXNETSCL	13	Perchloroethylene	24	Lognormal (3.78,7.08)
49	TXNETSFL	13	Perchloroethylene	24	Lognormal (2.14,2.14)
50	TXNETRSL	13	Perchloroethylene	24	Lognormal (1.40,1.65)
51	WOODOUTL	1	Perchloroethylene	24	Lognormal (0.53,1.99)
52	TM87B24L	2	Perchloroethylene	24	Lognormal (2.90,2.55)
53	TM87W24L	2	Perchloroethylene	24	Lognormal (4.06,3.08)
54	TM87S24L	2	Perchloroethylene	24	Lognormal (1.75,0.99)
55	TM84LAWL	3	Perchloroethylene	PM	Lognormal (11.20,9.80)
56	TM84LASL	3	Perchloroethylene	PM	Lognormal (1.86,1.34)
<u>57</u>	TM84CCSL	3	Perchloroethylene	PM	Lognormal (0.62,1.26)
<u> 58</u>	TXNETALL	13	Trichloroethylene	24	Lognormal (0.87,2.02)
59	TXNETSCL	13	Trichloroethylene	24	Lognormal (0.96,1.07)
60	TXNETSFL	13	Trichloroethylene	24	Lognormal (1.01,3.08)
61	TXNETRSL	13	Trichloroethylene	24	Lognormal (0.70,1.39)
62	TM87B24L	2	Trichloroethylene	24	Lognormal (0.16,0.14)
63	TM87W24L	2	Trichloroethylene	24	Lognormal (0.21,0.18)
64	TM87S24L	2	Trichloroethylene	24	Lognormal (0.11,0.05)
65	TM84LAWL	3	Trichloroethylene	PM	Lognormal (0.95,0.78)
66	TM84LASL	3	Trichloroethylene	PM	Lognormal (0.14,0.34)
67	TM84CCSL	3	Trichloroethylene	PM	Lognormal (0.12, 0.06)
68	CRIAQALL	10	Benzene	24	Lognormal (8.63,7.99)
69	CRIAQPGL°	10	Benzene	24	Lognormal (5.43,3.20)
70	CRIAQSCL°	10	Benzene	24	Lognormal (15.02,11.18)
71	CRIAQSDL°	10	Benzene	24	Lognormal (6.07,2.56)
72	CRIAQALL°	10	Nitrogen Dioxide	24	Lognormal (43.30,32.00)
73	CRIAQPGL°	10	Nitrogen Dioxide	24	Lognormal (33.90,24.50)
74	CRIAQSCL°	10	Nitrogen Dioxide	24	Lognormal (65.80,41.40)
<u>75</u>	CRIAQSDL°	10	Nitrogen Dioxide	24	Lognormal (39.50,22.60)
<u>76</u>	CRIAQALL <sup>a,c</sup>	10	Carbon Monoxide	24	Lognormal (1.10,1.40)
77	CRIAQPGL <sup>c</sup>	10	Carbon Monoxide	24	Lognormal (0.80,0.60)
<u>78</u> 79	CRIAQSCL°	10	Carbon Monoxide	24	Lognormal (2.20,2.30)
80	CRIAQSDL°	10	Carbon Monoxide	24	Lognormal (0.80,0.60)
	TM87WDYL		Benzene	AM	Lognormal (4.69,3.07)
81	TM87SDYL		Benzene	AM	Lognormal (3.45,2.38)
82 83	TM87BNTL		Benzene	PM	Lognormal (6.97,6.06)
84	TM87WNTL		Benzene	PM	Lognormal (9.58,6.83)
85	TM87SNTL		Benzene	PM	Lognormal (3.96,2.98)
<u>86</u>	TM87BDYL	<del></del>	Chloroform	AM	Lognormal (0.63,1.57)
87	TM87WDYL		Chloroform	AM	Lognormal (0.48,0.77)
88	TM87SDYL		Chloroform	AM	Lognormal (0.80,2.12)
89	TM87BNTL		Chloroform	PM	Lognormal (0.74,1.83)
90	TM87WNTL		Chloroform	PM	Lognormal (0.47,1.10)
91	TM87SNTL		Chloroform	PM	Lognormal (1.05,2.39)
92	TM87BDYL		Perchloroethylene	AM	Lognormal (2.61,1.83)
93	TM87WDYL TM87SDYL		Perchloroethylene		Lognormal (2.94,1.84)
	TIVIOTODIL	2	Perchloroethylene	AM	Lognormal (2.26,1.77)

Case Number         Ref         Pollutant         Averaging Period         Distribution Type (Data)           94         TM87RNTL         2         Perchloroethylene         PM         Lognormal (3.64,4.39)           95         TM87SNTL         2         Perchloroethylene         PM         Lognormal (1.24,0.87)           96         TM87SNTL         2         Pérchloroethylene         PM         Lognormal (1.24,0.87)           97         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           98         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           100         TM87SDYL         2         Trichloroethylene         PM         Lognormal (0.16,0.15)           101         TM87SDYL         2         Trichloroethylene         PM         Lognormal (0.28,0.29)           102         TM87SDYL         2         Trichloroethylene         PM         Lognormal (1.82,0.02)           103         CABENZ93         30         Benzene         24         Lognormal (1.82,0.02)           104         CABENZ93         30         Benzene         24         Lognormal (1.82,0.02)           105         CABENZ93         30         Benzene			Outdoors					
94         TM87BNTL         2         Perchloroethylene         PM         Lognormal (3.64,4.39)           95         TM87SNTL         2         Perchloroethylene         PM         Lognormal (1.24,0.87)           96         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.13,0.12)           98         TM87BDYL         2         Trichloroethylene         AM         Lognormal (0.10,0.7)           100         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.10,0.07)           100         TM87SDYL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.02)           103         CABEN.293         30         Benzene         24         Lognormal (1.86,2.16)           104         CABEN.293         30         Benzene         24         Lognormal (1.86,2.07)           105         CABEN.293         30         Benzene         24         Lognormal (1.82,2.08)           107         OABEN.293         30         Benzene		Case Name	Ref	Pollutant		Distribution Type (Data)		
95         TM87NTL         2         Perchloroethylene         PM         Lognormal (5.72,5.12)           96         TM87SNTL         2         Perchloroethylene         PM         Lognormal (0.13,0.12)           98         TM87WDYL         2         Trichloroethylene         AM         Lognormal (0.13,0.12)           99         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           100         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           103         CABENZ97         30         Benzene         24         Lognormal (0.20,0.20)           104         CABENZ99         30         Benzene         24         Lognormal (1.87,1.97)           105         CABENZ99         30         Benzene         24         Lognormal (1.82,0.0)           107         OABENZ93         30         Benzene		TM87BNTL	2	Perchloroethylene		Lognormal (3 64 4 39)		
96         TM87SNTL         2         Perchloroethylene         PM         Lognormal (1.24,0.87)           97         TM87BDYL         2         Trichloroethylene         AM         Lognormal (0.13,0.12)           98         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           100         TM87SDYL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.28,0.29)           102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.28,0.29)           103         CABENZ98         30         Benzene         24         Lognormal (1.87,1.97)           105         CABENZ98         30         Benzene         24         Lognormal (1.87,1.97)           105         CABENZ93         30         Benzene         24         Lognormal (1.82,2.08)           107         OABENZ93         30         Benzene         24         Lognormal (1.89,2.07)           105         CABENZ93         30         Benzene         24         Lognormal (1.87,1.91           107         OABENZ93         30         Benzene         24		TM87WNTL	2					
97         TM87BDYL         2         Trichloroethylene         AM         Lognormal (0.13,0.12)           98         TM87WDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           99         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.11,0.07)           100         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.12,0.10)           103         CABENZ97         30         Benzene         24         Lognormal (1.86,2.16)           104         CABENZ98         30         Benzene         24         Lognormal (1.86,2.07)           105         CABENZ99         30         Benzene         24         Lognormal (1.86,2.07)           106         CABENZ99         30         Benzene         24         Lognormal (1.86,2.07)           106         CABENZ99         30         Benzene         24         Lognormal (1.86,2.07)           106         CABENZ93         30         Benzene         24         Lognormal (1.81,17,108)           109         OABENZ93         30         Benzene         24         <	96	TM87SNTL	2					
98         TM87XDYL         2         Trichloroethylene         AM         Lognormal (0.16,0.15)           99         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.10,007)           100         TM87BNTL         2         Trichloroethylene         PM         Lognormal (0.28,0.29)           101         TM87XNTL         2         Trichloroethylene         PM         Lognormal (0.12,0.10)           103         CABENZ97         30         Benzene         24         Lognormal (1.86,2.16)           104         CABENZ98         30         Benzene         24         Lognormal (1.86,2.16)           104         CABENZ98         30         Benzene         24         Lognormal (1.86,2.07)           105         CABENZ99         30         Benzene         24         Lognormal (1.82,2.08)           107         OABENZ93         30         Benzene         24         Lognormal (1.19,1.34)           108         OABENZ93         30         Benzene         24         Lognormal (1.17,1.08)           109         OABENZ93         30         Benzene         24         Lognormal (1.20,1.27)           111         SFBENZ93         30         Benzene         24         Lognorma		TM87BDYL	2		·			
99         TM87SDYL         2         Trichloroethylene         AM         Lognormal (0.21,0.07)           100         TM87BNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.20,0.29)           102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.20,0.20)           103         CABENZ98         30         Benzene         24         Lognormal (1.87,1.97)           105         CABENZ98         30         Benzene         24         Lognormal (1.87,1.97)           105         CABENZ99         30         Benzene         24         Lognormal (1.87,1.97)           106         CABENZ9         30         Benzene         24         Lognormal (1.87,1.91)           106         CABENZ93         30         Benzene         24         Lognormal (1.19,1.34)           108         OABENZ93         30         Benzene         24         Lognormal (1.17,1.08)           109         OABENZ99         30         Benzene         24         Lognormal (1.20,1.27)           111         SFBENZ93         30         Benzene         24         <		TM87WDYL	2					
100         TM87BNTL         2         Trichloroethylene         PM         Lognormal (0.20,0.23)           101         TM87WNTL         2         Trichloroethylene         PM         Lognormal (0.28,0.29)           102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.12,0.10)           103         CABENZ97         30         Benzene         24         Lognormal (1.82,16)           104         CABENZ98         30         Benzene         24         Lognormal (1.87,197)           105         CABENZ99         30         Benzene         24         Lognormal (1.82,2.08)           106         CABENZ93         30         Benzene         24         Lognormal (1.82,2.08)           107         OABENZ93         30         Benzene         24         Lognormal (1.91,134)           108         OABENZ98         30         Benzene         24         Lognormal (1.71,108)           109         OABENZ99         30         Benzene         24         Lognormal (1.76,174)           110         OABENZ98         30         Benzene         24         Lognormal (1.76,174)           111         SFBENZ98         30         Benzene         24         Lognormal (1.76,174)<	99	TM87SDYL	2					
101   TM87VNTL   2   Trichloroethylene   PM   Lognormal (0.28,0.29)   102   TM87SNTL   2   Trichloroethylene   PM   Lognormal (0.12,0.10)   103   CABENZ97   30   Benzene   24   Lognormal (1.86,2.16)   104   CABENZ98   30   Benzene   24   Lognormal (1.87,1.97)   105   CABENZ99   30   Benzene   24   Lognormal (1.88,2.07)   105   CABENZ99   30   Benzene   24   Lognormal (1.88,2.07)   106   CABENZ97   30   Benzene   24   Lognormal (1.82,2.08)   107   OABENZ97   30   Benzene   24   Lognormal (1.19,1.34)   108   OABENZ98   30   Benzene   24   Lognormal (1.17,1.08)   109   OABENZ99   30   Benzene   24   Lognormal (1.22,1.38)   110   OABENZ99   30   Benzene   24   Lognormal (1.20,1.27)   111   SFBENZ97   30   Benzene   24   Lognormal (1.20,1.27)   112   SFBENZ98   30   Benzene   24   Lognormal (1.87,1.75)   113   SFBENZ99   30   Benzene   24   Lognormal (1.87,1.75)   114   SFBENZ   30   Benzene   24   Lognormal (1.84,1.82)   115   SCBENZ99   30   Benzene   24   Lognormal (2.04,2.37)   116   SCBENZ99   30   Benzene   24   Lognormal (2.63,2.13)   116   SCBENZ99   30   Benzene   24   Lognormal (2.63,2.13)   117   SCBENZ99   30   Benzene   24   Lognormal (2.63,2.46)   118   SCBENZ99   30   Benzene   24   Lognormal (2.63,2.46)   119   CABAP99   30   Benzene   24   Lognormal (2.63,2.46)   119   CABAP99   30   Benzene   24   Lognormal (0.15,0.30)   120   CABAP98   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)   121   CABAP99   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)   122   CABAP99   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)   125   OABAP97   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)   125   OABAP97   30   Benzo(a)pyrene   24   Lognormal (0.16,0.35)   125   OABAP99   30   Benzo(a)pyrene   24   Lognormal (0.16,0.35)   125   OABAP99   30   Benzo(a)pyrene   24   Lognormal (0.10,0.65)   125   OABAP99   30   Benzo(a)pyrene   24   Lognormal (0.10,0.05)   126   OABAP9   30   Benzo(a)pyrene   24   Lognormal (0.10,0.05)   128   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.05)   130   SFBAP9   30		TM87BNTL	2					
102         TM87SNTL         2         Trichloroethylene         PM         Lognormal (0.12,0.10)           103         CABENZ97         30         Benzene         24         Lognormal (1.86,2.16)           104         CABENZ99         30         Benzene         24         Lognormal (1.82,1.97)           105         CABENZ99         30         Benzene         24         Lognormal (1.82,1.97)           106         CABENZ97         30         Benzene         24         Lognormal (1.82,2.08)           107         OABENZ97         30         Benzene         24         Lognormal (1.19,1.34)           108         OABENZ98         30         Benzene         24         Lognormal (1.71,1.08)           109         OABENZ98         30         Benzene         24         Lognormal (1.20,1.27)           111         SFBENZ97         30         Benzene         24         Lognormal (1.76,174)           112         SFBENZ98         30         Benzene         24         Lognormal (1.82,1.23)           113         SFBENZ99         30         Benzene         24         Lognormal (2.63,2.37)           114         SFBENZ99         30         Benzene         24         Lognormal (2.63,2.43) </td <td>******</td> <td>TM87WNTL</td> <td>2</td> <td>Trichloroethylene</td> <td></td> <td></td>	******	TM87WNTL	2	Trichloroethylene				
103		TM87SNTL	2	Trichloroethylene				
104   CABENZ98   30   Benzene   24   Lognormal (1.87,1.97)	103	CABENZ97	30					
105		CABENZ98	30	Benzene				
106         CABENZ®         30         Benzene         24         Lognormal (1.82,2.08)           107         OABENZ97         30         Benzene         24         Lognormal (1.19,1.34)           108         OABENZ98         30         Benzene         24         Lognormal (1.17,1.08)           109         OABENZ99         30         Benzene         24         Lognormal (1.22,1.38)           110         OABENZ         30         Benzene         24         Lognormal (1.20,1.27)           111         SFBENZ98         30         Benzene         24         Lognormal (1.76,174)           112         SFBENZ98         30         Benzene         24         Lognormal (1.76,174)           113         SFBENZ99         30         Benzene         24         Lognormal (1.76,174)           114         SFBENZ99         30         Benzene         24         Lognormal (1.87,1.75)           115         SCBENZ97         30         Benzene         24         Lognormal (2.04,2.37)           116         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)		CABENZ99	30	Benzene	<del></del>			
107		CABENZ <sup>a</sup>	30					
108		OABENZ97	30					
109		OABENZ98	30	Benzene				
110   OABENZ   30   Benzene   24   Lognormal (1.20,1.27)     111   SFBENZ97   30   Benzene   24   Lognormal (1.76,174)     112   SFBENZ98   30   Benzene   24   Lognormal (1.76,174)     113   SFBENZ99   30   Benzene   24   Lognormal (2.04,2.37)     114   SFBENZ   30   Benzene   24   Lognormal (2.04,2.37)     115   SCBENZ97   30   Benzene   24   Lognormal (2.63,2.13)     116   SCBENZ98   30   Benzene   24   Lognormal (2.62,2.46)     117   SCBENZ99   30   Benzene   24   Lognormal (2.62,2.46)     118   SCBENZ   30   Benzene   24   Lognormal (2.59,2.43)     119   CABAP97   30   Benzene   24   Lognormal (2.59,2.43)     119   CABAP97   30   Benzo(a)pyrene   24   Lognormal (0.15,0.30)     120   CABAP98   30   Benzo(a)pyrene   24   Lognormal (0.14,0.28)     121   CABAP99   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)     122   CABAP8   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)     123   OABAP97   30   Benzo(a)pyrene   24   Lognormal (0.16,0.32)     124   OABAP98   30   Benzo(a)pyrene   24   Lognormal (0.18,0.45)     125   OABAP98   30   Benzo(a)pyrene   24   Lognormal (0.18,0.45)     126   OABAP   30   Benzo(a)pyrene   24   Lognormal (0.17,0.42)     127   SFBAP97   30   Benzo(a)pyrene   24   Lognormal (0.10,0.65)     128   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)     128   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)     129   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)     129   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.20)     130   SFBAP   30   Benzo(a)pyrene   24   Lognormal (0.10,0.20)     131   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.20)     133   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.20)     134   SCBAP9   30   Benzo(a)pyrene   24   Lognormal (0.14,0.23)     135   CACHL98   30   Chloroform   24   Lognormal (0.15,0.25)     136   CACHL98   30   Chloroform   24   Lognormal (0.15,0.25)     137   CACHL99   30   Chloroform   24   Lognormal (0.15,0.01)	109	OABENZ99	30	Benzene				
111         SFBENZ97         30         Benzene         24         Lognormal (1.76,174)           112         SFBENZ98         30         Benzene         24         Lognormal (2.04,2.37)           113         SFBENZ99         30         Benzene         24         Lognormal (2.04,2.37)           114         SFBENZ97         30         Benzene         24         Lognormal (2.62,2.13)           115         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ99         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ9         30         Benzene         24         Lognormal (2.59,2.43)           118         SCBENZ         30         Benzone         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP3         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)<	110	OABENZ	30	T				
112   SFBENZ98   30   Benzene   24   Lognormal (1.87,1.75)   113   SFBENZ99   30   Benzene   24   Lognormal (2.04,2.37)   114   SFBENZ   30   Benzene   24   Lognormal (2.04,2.37)   115   SCBENZ97   30   Benzene   24   Lognormal (2.63,2.13)   116   SCBENZ98   30   Benzene   24   Lognormal (2.62,2.46)   117   SCBENZ99   30   Benzene   24   Lognormal (2.62,2.46)   118   SCBENZ   30   Benzene   24   Lognormal (2.62,2.46)   119   CABAP97   30   Benzene   24   Lognormal (2.59,2.43)   119   CABAP98   30   Benzo(a)pyrene   24   Lognormal (0.15,0.30)   120   CABAP98   30   Benzo(a)pyrene   24   Lognormal (0.18,0.39)   121   CABAP99   30   Benzo(a)pyrene   24   Lognormal (0.14,0.28)   122   CABAP8   30   Benzo(a)pyrene   24   Lognormal (0.14,0.28)   123   OABAP97   30   Benzo(a)pyrene   24   Lognormal (0.18,0.45)   124   OABAP98   30   Benzo(a)pyrene   24   Lognormal (0.18,0.45)   125   OABAP99   30   Benzo(a)pyrene   24   Lognormal (0.24,0.65)   125   OABAP99   30   Benzo(a)pyrene   24   Lognormal (0.17,0.42)   126   OABAP9   30   Benzo(a)pyrene   24   Lognormal (0.17,0.42)   127   SFBAP97   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)   128   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)   128   SFBAP98   30   Benzo(a)pyrene   24   Lognormal (0.10,0.16)   129   SFBAP9   30   Benzo(a)pyrene   24   Lognormal (0.10,0.20)   130   SFBAP   30   Benzo(a)pyrene   24   Lognormal (0.12,0.20)   131   SCBAP97   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   132   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   133   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   135   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   135   SCBAP98   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   136   SCBAP9   30   Benzo(a)pyrene   24   Lognormal (0.15,0.27)   136   SCBAP9   30   Benzo(a)pyrene   24   Lognormal (0.15,0.25)   135   CACHL97   30   Chloroform   24   Lognormal (0.15,0.15)   136   CACHL98   30   Chloroform   24   Lognormal (0.15,0.15)   137   CACHL99   30   Chloroform   2	111	SFBENZ97	30					
113         SFBENZ99         30         Benzene         24         Lognormal (2.04,2.37)           114         SFBENZ         30         Benzene         24         Lognormal (1.84,1.82)           115         SCBENZ97         30         Benzene         24         Lognormal (2.63,2.13)           116         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ99         30         Benzene         24         Lognormal (2.43,2.69)           118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP93         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal	112	SFBENZ98	30					
114         SFBENZ         30         Benzene         24         Lognormal (1.84,1.82)           115         SCBENZ97         30         Benzene         24         Lognormal (2.63,2.13)           116         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ99         30         Benzene         24         Lognormal (2.43,2.69)           118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Logn	113	SFBENZ99	30	·				
115         SCBENZ97         30         Benzene         24         Lognormal (2.63,2.13)           116         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ99         30         Benzene         24         Lognormal (2.43,2.69)           118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP9         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP93         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP93         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP9         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24 <td< td=""><td>114</td><td>SFBENZ</td><td>30</td><td>Benzene</td><td></td><td></td></td<>	114	SFBENZ	30	Benzene				
116         SCBENZ98         30         Benzene         24         Lognormal (2.62,2.46)           117         SCBENZ99         30         Benzene         24         Lognormal (2.43,2.69)           118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP9         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           127         SFBAP98         30         Benzo(a)pyrene         24	115	SCBENZ97	30	1	~ <del>~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~</del>			
117         SCBENZ99         30         Benzene         24         Lognormal (2.43,2.69)           118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           125         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24 <td><u>116</u></td> <td>SCBENZ98</td> <td>30</td> <td>·</td> <td></td> <td></td>	<u>116</u>	SCBENZ98	30	·				
118         SCBENZ         30         Benzene         24         Lognormal (2.59,2.43)           119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP3         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene	117	SCBENZ99	30		<del></del>			
119         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP3         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP9         30         Benzo(a)pyrene	118	SCBENZ	30		- <del> </del>			
120         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP98         30         Benzo(a)pyrene	119	CABAP97	30	Benzo(a)pyrene	<del></del>			
121         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           122         CABAPa         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP98         30         Benzo(a)pyrene	120	CABAP98	30					
122         CABAPa         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene	121	CABAP99	30		<del></del>			
123         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene	122	CABAP <sup>a</sup>	30		<del></del>			
124         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           135         CACHL97         30         Chloroform <td< td=""><td>123</td><td>OABAP97</td><td>30</td><td></td><td><del></del></td><td></td></td<>	123	OABAP97	30		<del></del>			
125         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24<	124	OABAP98	30		<u> </u>			
126         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           137         CACHL99         30         Chloroform         24		OABAP99	30		<u> </u>			
127         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24		OABAP	30	Benzo(a)pyrene				
128         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	127	SFBAP97	30		<del></del>			
129         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	128	SFBAP98	30					
130         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	129	SFBAP99	30					
131         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	130	SFBAP			~			
132         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	131	SCBAP97						
133         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	132	SCBAP98						
134         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	133	SCBAP99						
135         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)	134	SCBAP						
136         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)		CACHL97						
137         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           138         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)		CACHL98						
138 CACHL <sup>a</sup> 30 Chloroform 24 Lognormal (0.20,0.19)		CACHL99						
400		CACHL						
	139	OACHL97						

Outdoors						
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type (Data)	
140	OACHL98	30	Chloroform	24	Lognormal (0.25,0.03)	
141	OACHL99	30	Chloroform	24	Lognormal (0.25,0.03)	
142	OACHL	30	Chloroform	24	Lognormal (0.27,0.09)	
143	SFCHL97	30	Chloroform	24	Lognormal (0.09,0.08)	
144	SFCHL98	30	Chloroform	24	Lognormal (0.07,0.04)	
145	SFCHL99	30	Chloroform	24	Lognormal (0.25,0.03)	
146	SFCHL	30	Chloroform	24	Lognormal (0.09,0.08)	
147	SCCHL97	30	Chloroform	24	Lognormal (0.25,0.02)	
148	SCCHL98	30	Chloroform	24	Lognormal (0.25,0.04)	
149	SCCHL99	30	Chloroform	24	Lognormal (0.26,0.06)	
150	SCCHL	30	Chloroform	24	Lognormal (0.25,0.04)	
151	CAFORM97	30	Formaldehyde	24	Lognormal (4.85,4.31)	
152	CAFORM98	30	Formaldehyde	24	Lognormal (5.22,4.83)	
153	CAFORM99	30	Formaldehyde	24	Lognormal (5.29,4.60)	
154	CAFORMª	30	Formaldehyde	24	Lognormal (5.13,4.60)	
155	OAFORM97	30	Formaldehyde	24	Lognormal (5.03,5.16)	
156	OAFORM98	30	Formaldehyde	24	Lognormal (5.00,4.66)	
157	OAFORM99	30	Formaldehyde	24	Legnormal (4.19,3.32)	
158	OAFORM	30	Formaldehyde	24	Lognormal (4.74,4.36)	
159	SFFORM97	30	Formaldehyde	24	Lognormal (2.34,1.44)	
160	SFFORM98	30	Formaldehyde	24	Lognormal (2.30,1.81)	
161	SFFORM99	30	Formaldehyde	24	Lognormal (2.61,2.07)	
162	SFFORM	30	Formaldehyde	24	Lognormal (2.40,1.76)	
163	SCFORM97	30	Formaldehyde	24	Lognormal (5.38,3.54)	
164	SCFORM98	30	Formaldehyde	24	Normal (5.80,3.27)	
165	SCFORM99	30	Formaldehyde	24	Lognormal (6.59,4.89)	
166	SCFORM	30	Formaldehyde	24	Lognormal (6.06,4.41)	
167	CATETR97	30	Perchloroethylene	24	Lognormal (0.78,0.96)	
168	CATETR98	30	Perchloroethylene	24	Lognormal (0.70,0.86)	
169	CATETR99	30	Perchloroethylene	24	Lognormal (0.76,0.68)	
170	CATETR <sup>a</sup>	30	Perchloroethylene	24	Lognormal (0.74,0.88)	
171	OATETR97	30	Perchloroethylene	24	Lognormal (0.46,0.24)	
172	OATETR98	30	Perchloroethylene	24	Lognormal (0.42,0.18)	
173	OATETR99	30	Perchloroethylene	24	Lognormal (0.48,0.26)	
174	OATETR	30	Perchloroethylene	24	Lognormal (0.45,0.23)	
175	SFTETR97	30	Perchloroethylene	24	Lognormal (0.75,1.10)	
176	SFTETR98	30	Perchloroethylene	24	Lognormal (0.65,0.93)	
177	SFTETR99	30	Perchloroethylene	24	Lognormal (0.43,0.18)	
178	SFTETR	30	Perchloroethylene	24	Lognormal (0.67,0.91)	
179	SCTETR97	30	Perchloroethylene	24	Lognormal (1.66,1.75)	
180	SCTETR98	30	Perchloroethylene	24	Lognormal (1.33,1.61)	
181	SCTETR99	30	Perchloroethylene	24	Lognormal (1.49,1.59)	
182	SCTETR	30	Perchloroethylene	24	Lognormal (1.49,1.68)	
183	CATRIC97	30	Trichloroethylene	24	Lognormal (0.30,0.15)	
184	CATRIC98	30	Trichloroethylene	24	Lognormal (0.27,0.09)	
185	CATRIC99	30	Trichloroethylene	24	Lognormal (0.33,0.16)	
	<u> </u>				(continued)	

	Outdoors								
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type (Data)				
186	CATRIC	30	Trichloroethylene	24	Lognormal (0.30,0.13)				
187	OATRIC97	30	Trichloroethylene	24	Lognormal (0.28,0.04)				
188	OATRIC98	30	Trichloroethylene	24	Lognormal (0.28,0.04)				
189	OATRIC99	30	Trichloroethylene	24	Lognormal (0.27,0.03)				
190	OATRIC	30	Trichloroethylene	24	Lognormal (0.28,0.04)				
191	SFTRIC97	30	Trichloroethylene	24	Lognormal (0.29,0.17)				
192	SFTRIC98	30	Trichloroethylene	24	Lognormal (0.24,0.06)				
193	SFTRIC99	30	Trichloroethylene	24	Lognormal (0.27,0.00)				
194	SFTRIC	30	Trichloroethylene	24	Lognormal (0.27,0.11)				
195	SCTRIC97	30	Trichloroethylene	24	Lognormal (0.40,0.24)				
196	SCTRIC98	30	Trichloroethylene	24	Lognormal (0.36,0.19)				
197	SCTRIC99	30	Trichloroethylene	24	Lognormal (0.45,0.39)				
198	SCTRIC	30	Trichloroethylene	24	Lognormal (0.40,0.27)				

<sup>&</sup>lt;sup>a</sup> Indicates case marked as default. See Table B-7a for recommended weights for default cases.

Table B-7a Recommended Weights (in Percents) for Default Cases for Outdoors

	24-Hour		Day Tim	е	Night Time		
	Case Name (#)	Weight	Case Name (#)	Weight	Case Name (#)	Weight	
Benzene	CABENZ (106)	100		W 1.522			
Benzo(a)pyrene	CABAP (122)	100	PTMDYL (16)	100	PTMNTL (17)	100	
Carbon Monoxide	CRIAQALL (76)	100				e de la contraction de la cont	
Chloroform	CACHL (138)	100					
Formaldehyde	CAFORM (154)	100					
Nitrogen Dioxide	HARVLAL (36)	100					
PM10	PTEAMFL (44)	100	PTEAMFL (45)	100	PTEAMFL (46)	100	
Perchloroethylene	CATETR (170)	100					
(Tetrachloroethylene) Trichloroethylene	CATRIC (186)	100					

<sup>&</sup>lt;sup>b</sup> Data for these cases are based on week-long measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.

<sup>&</sup>lt;sup>c</sup> Data for these cases are based on 48-hour measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.

#### **Level 3 Inputs**

Pollutant-specific inputs available for Level 3 of the model are summarized in Table B-8. All inputs are specific to the residential environment. Indoor sources, penetration factors and indoor sinks are available for three pollutants—benzo(a)pyrene, chloroform and nitrogen dioxide. Outdoor concentration distributions (based on daily averages) are available for all pollutants in the model except total PAHs. As noted in a footnote to the table, inputs are also available for volumes and air exchange rates, but these are not pollutant-specific.

Of the six categories of indoor sources (see Section 4.1), model inputs are currently available for two types--long-term (no loading) sources (Table B-9) and frequent (no loading) sources (Table B-10). Each of the two tables lists all inputs for each case name associated with each pollutant.. Distributional data on volumes, air exchange rates, penetration factors, indoor reactive decay and indoor adsorption are summarized in Tables B-11 through B-15, respectively. Outdoor concentrations for level 3 (24 hour average only) are re summarized in Table B-16.

Table B-8 Summary of Pollutant-specific Inputs\* Available for Model Level 3

	Long- Term (No	Frequent	Outdoor	B	Indoor Sinks		
Pollutant	Loading) Sources	(No Loading) Sources	Concs (Daily)	Penetration Factors	RD <sup>a</sup> (k <sub>1</sub> )	AD <sup>b</sup> (k <sub>2</sub> )	Dep <sup>c</sup> (k <sub>3</sub> )
Benzene	•	·.	, x				
Benzo(a)pyrene	<b>, x</b>		x	X	x		
Carbon Monoxide			X				
Chloroform		X	X	X	X		
Formaldehyde			X		www.iata	en Too area en la	Elizabeth (* 1815
Nitrogen Dioxide	×	X	1 x	X	x		
PM10		1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	X			200000000000000000000000000000000000000	######################################
Perchloroethylene			X			X	
Trichloroethylene		ye uma maa maanaa ka gaay ah	X		#1,2507 (Gentle/45		
Total PAHs			x				

<sup>\*</sup>Inputs for volumes and air exchange rates are also available, but these are not pollutantspecific

 $a k_1 = Reactive Decay$ 

<sup>&</sup>lt;sup>b</sup>  $k_2$  = Net Surface Adsorption Rate = adsorption – de-adsorption

<sup>&</sup>lt;sup>c</sup> k₃ = Net Deposition Rate = deposition - resuspension

Table B-9 Inputs for Long Term (No Loading) Indoor Sources (Level 3)

Pollutant	Case Name	Ref	Input Parameter	Distribution/Value(s)
Benzo(a)pyrene	SOURCE1	4	Percent of Cases	28
		4	Quantity Present	Normal (1, 0)
		A1b	When Installed	Normal (12, 0)
		4	Initial Emission Rate	Lognormal (390, 390)
		A2c	Decline in Rate	Normal (0, 0)
	SOURCE2a	4	Initial Emission Rate	Lognormal (390, 1285)
	SOURCE3a	4	Initial Emission Rate	Percentile (0, 5; 50, 10; 75, 20; 80, 66; 85, 218; 90, 721; 95, 2383; 100, 8800)
Nitrogen Dioxide	PILOT	7	Percent of Cases	68.1 (Linked to COOKING)
		14	Quantity Present	Percentile (0, 128.8; 25, 257.5; 50, 343.3; 75, 429.2; 100, 643.8)
				Normal (12, 0)
		A1b	When Installed	Normal (9.15, 2.3)
		15	Initial Emission Rate	Normal (0, 0)
		A2c	Decline in Rate	

<sup>&</sup>lt;sup>a</sup> Other inputs same as for SOURCE1.

<sup>&</sup>lt;sup>b</sup> Arbitrary values; for a constant emission rate, as assumed in this case, the model does not use this input parameter.

<sup>&</sup>lt;sup>c</sup> The appropriate value is zero when a constant emission rate is assumed within each modeled structure.

Table B-10 Inputs for Frequent (No Loading) Indoor Sources (Level 3)

Pollutant	Case Name	Ref	Input Parameter	Distribution/Value(s)
Chloroform	ALL	A1a	Percent of Cases	100
		16	Quantity Present	Lognormal (99.2, 24.8)
		A2b	Episodes per Day	Lognormal (10, 5)
		A1a	Start Timec	(1, 1, 1, 1, 1, 2, 4, 6, 8, 6, 4, 4,
	'			6, 4, 4, 4, 6, 8, 8, 8, 6, 4, 2, 1)
				Normal (1, 0)
		A2b	Duration	Yes
		A1a	Overlapping Episodes	Lognormal (5.2, 3.0)
		2	Initial Emission Rate	Normal (0, 0)
		A3d	Decline in Rate	
	ALL2e	2	Initial Emission Rate	Lognormal (8.5, 2.6)
Nitrogen	COOKING	7	Percent of Cases	73.3
Dioxide		14	Quantity Present	Lognormal (150, 50)
		14	Episodes per Day	Frequency (15%-0; 50%-1, 20%-2; 15%-3)
		A1a	Start Timec	(0, 0, 0, 0, 0, 0, 0, 26, 0, 0, 0, 0, 22, 0, 0, 0, 0, 0, 52, 0, 0, 0, 0, 0) Lognormal (33.3, 33.3)
		17	Duration	No
		A1a	Overlapping Episodes	Normal (9.15, 2.3)
	Tilde et e	15	Initial Emission Rate	Normal (0, 0)
		A3d	Decline in Rate	
THE LAW IN	RANGEHT	17	Percent of Cases	2.8 (Linked to COOKING)
7 M + 5 A		A1a	Quantity Present	Normal (300, 0)
		17	Episodes per Day	Frequency (66%-0; 34%-1)
		A1a	Start Timec	(0, 0, 0, 0, 0, 25, 25, 0, 0, 0, 0,
				0, 0, 0, 0, 0, 0, 0, 0, 25, 25, 0, 0, 0, 0)
		17	Duration	Lognormal (144, 72)
		A1a	Overlapping Episodes	No
		15	Initial Emission Rate	Normal (9.15, 2.3)
		A3d	Decline in Rate	Normal (0, 0)

<sup>&</sup>lt;sup>a</sup>Assumed value based on professional judgment.

<sup>&</sup>lt;sup>b</sup> Values were chosen such that the product of episodes per day times quantity present times duration of use was consistent with the average quantity used per day, as determined from reference 16.

<sup>&</sup>lt;sup>c</sup> Percent share for each of 24 hourly periods, starting with midnight to 1:00 a.m.

<sup>&</sup>lt;sup>d</sup> The appropriate value is zero when a constant emission rate is assumed within each modeled structure.

<sup>°</sup> Other inputs same as for ALL.

Table B-11 Inputs for Volumes (Level 3)

. Case Name	Ref	Distribution/Value(s)
RTI-TMLA	2, 20	Lognormal (274.9, 110.6)
SOCAL-3	8, 20	Lognormal (309.5, 159.8)
ADM	21	Lognormal (354, 101)

Table B-12 Inputs for Air Exchange Rates (Level 3)

Case Name	Ref	Distribution/Value(s)
TEAMLA1	2, 20	Lognormal (0.94, 0.82)
TEAMLA2	2, 20	Lognormal (2.83, 2.54)
SOCAL1	8	Lognormal (0.78, 0.63)
SOCAL2	8	Lognormal (1.51, 1.47)
SOCAL3	8	Lognormal (0.58, 0.47)
CALIAQSC	10	Lognormal (0.77, 0.57)
ADM	21	Lognormal (0.70, 0.52)
PTEAM	4	Lognormal (1.25, 1.02)
LIGO1 (public access buildings)	34	Lognormal(1.15, 1.03)
WILS1	35	Lognormal (0.47,0.34)
WILS2	35	Lognormal (0.79,0.57)
WILS3	35	Lognormal (0.54,0.34)

**Table B-13 Inputs for Penetration Factors (Level 3)** 

Pollutant	Case Name	Ref	Distribution/Value(s)
Benzo(a)pyrene	PEN1	4	Normal (0.6, 0)
Chloroform	PEN1	A1a	Normal (1, 0)
Nitrogen Dioxide	PEN1	18	Normal (1, 0)
Benzene	LEW1	31	Normal (1, 0)

<sup>&</sup>lt;sup>a</sup> Assumed value based on professional judgment.

Table B-14 Inputs for Indoor Sinks – Reactive Decay (Level 3)

Pollutant	Case Name	Ref	Distribution/Value(s)
Benzo(a)pyrene	SINK1	4	Normal (0, 0)
Chloroform	SINK1	A1a	Normal (0, 0)
Nitrogen Dioxide	SINK1	15	Lognormal (0.5, 0.3)
Nitrogen Dioxide	SINK2	18, 19	Lognormal (0.8, 0.3)
Nitrogen Dioxide	SPIC1	32	Lognormal (1,18, 0.16)

<sup>&</sup>lt;sup>a</sup> Assumed value based on professional judgment.

Table B-15 Inputs for Indoor Sinks – Adsorption (Level 3)

Pollutant	Case Name	Ref	Distribution/Value(s)
Perchloroethylene	COLO1 (empty chamber)	33	Normal (0.15, 0)
Perchloroethylene	COLO2 (carpet)	33	Normal (0.17, 0)
Perchloroethylene	COLO3 (blown vinyl)	33	Normal (0.17, 0)
Perchloroethylene	COLO4 (gypsum board)	33	Normal (0.06, 0)

Table B-16 Concentration Distributions for Outdoors (Level 3)

Case Number         Case Name         Ref         Pollutant         Averaging Period         Distribution Type (Data)           3         TXNETALL         13         Benzene         24         Lognormal (8.04,6.78)           4         TXNETSFL         13         Benzene         24         Lognormal (7.27,6.48)           5         TXNETSFL         13         Benzene         24         Lognormal (7.27,6.48)           6         TXNETSFL         13         Benzene         24         Lognormal (7.27,6.48)           7         WOODOUTL         1         Benzene         24         Lognormal (7.20,6.62)           3         TM87824L         2         Benzene         24         Lognormal (6.41,3.83)           10         TM87824L         2         Benzene         24         Lognormal (6.41,3.83)           10         TM87824L         2         Benzene         24         Lognormal (0.90,50)           11         11         PTM24L         4         Benzo(a)Pyrene         24         Lognormal (0.90,03,03)           12         TXNETALL         13         Chloroform         24         Lognormal (0.18,0.16)           14         TXNETSCL         13         Chloroform         24         Logn	Outdoors							
3   TXNETALL		Case Name	Ref			Distribution Type (Data)		
5         TXNETSFL         13         Benzene         24         Lognormal (7.27,6.48)           6         TXNETRSL         13         Benzene         24         Lognormal (7.27,6.48)           7         WOODOUTL         1         Benzene         24         Lognormal (7.27,6.48)           9         TM87B24L         2         Benzene         24         Lognormal (5.10,3.46)           9         TM87W24L         2         Benzene         24         Lognormal (6.41,3.83)           10         TM87S24L         2         Benzene         24         Lognormal (6.41,3.83)           10         TM87S24L         2         Benzene         24         Lognormal (0.30,0.36)           12         TXNETALL         13         Chloroform         24         Lognormal (0.19,0.59)           13         TXNETSCL         13         Chloroform         24         Lognormal (0.17,0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.17,0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.21,0.86)           16         TM87W24L         2         Chloroform         24         Lognormal (0.44,0.80)	3	TXNETALL	13	Benzene		Lognormal (8.04,6.78)		
5         TXNETSFL         13         Benzene         24         Lognormal (7.27,6.48)           6         TXNETRSL         13         Benzene         24         Lognormal (7.26,5.83)           7         WOODOUTL         1         Benzene         24         Lognormal (6.10,3.46)           9         TM87B24L         2         Benzene         24         Lognormal (6.41,3.83)           10         TM87S24L         2         Benzene         24         Lognormal (0.30,0.36)           11         PTM24L         4         Benzo(a)Pyrene         24         Lognormal (0.30,0.36)           12         TXNETALL         13         Chloroform         24         Lognormal (0.19,0.59)           13         TXNETSCL         13         Chloroform         24         Lognormal (0.19,0.59)           14         TXNETSFL         13         Chloroform         24         Lognormal (0.19,0.59)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.17,0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.21,0.86)           16         TM87824L         2         Chloroform         24         Lognormal (0.49,0.80)	4	TXNETSCL	13	Benzene	24	Lognormal (10.20.7.07)		
6         TXNETRSL         13         Benzene         24         Lognormal (7.46,5.83)           7         WOODOUTL         1         Benzene         24         Lognormal (5.10,3.46)           9         TM87B24L         2         Benzene         24         Lognormal (5.10,3.46)           9         TM87W24L         2         Benzene         24         Lognormal (3.75,2.41)           11         PTM24L         4         Benzo(a)Pyrene         24         Lognormal (0.30,0.36)           12         TXNETALL         13         Chloroform         24         Lognormal (0.19,0.59)           13         TXNETSCL         13         Chloroform         24         Lognormal (0.18,0.16)           14         TXNETSCL         13         Chloroform         24         Lognormal (0.17,0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.49,0.80)           16         TM87B24L         2         Chloroform         24         Lognormal (0.49,0.80)           18         TM87S24L         2         Chloroform         24         Lognormal (0.49,0.80)           18         TM87W24L         2         Chloroform         24         Lognormal (0.49,0.80)	5.	TXNETSFL	13	Benzene	24			
Separate		TXNETRSL	13	Benzene	24			
9 TM87W24L 2 Benzene 24 Lognormal (6.41,3.83) 10 TM87S24L 2 Benzene 24 Lognormal (3.75,2.41) 11 PTM24L 4 Benzo(a)Pyrene 24 Lognormal (0.30,0.36) 12 TXNETALL 13 Chloroform 24 Lognormal (0.19,0.59) 13 TXNETSCL 13 Chloroform 24 Lognormal (0.18,0.16) 14 TXNETSFL 13 Chloroform 24 Lognormal (0.18,0.16) 15 TXNETRSL 13 Chloroform 24 Lognormal (0.21,0.86) 16 TM87B24L 2 Chloroform 24 Lognormal (0.21,0.86) 16 TM87B24L 2 Chloroform 24 Lognormal (0.64,1.11) 17 TM87W24L 2 Chloroform 24 Lognormal (0.49,0.80) 18 TM87S24L 12 Chloroform 24 Lognormal (0.79,1.36) 19 TXNETSCL 13 Benzo(a)Pyrene 24 Lognormal (0.84,1.87) 20 TXNETSCL 13 Benzo(a)Pyrene 24 Lognormal (0.42,0.74) 21 TXNETSCL 13 Benzo(a)Pyrene 24 Lognormal (0.42,0.74) 22 TXNETSCL 13 Benzo(a)Pyrene 24 Lognormal (0.40,3.20) 23 TOXALL 13 Formaldehyde 24 Lognormal (1.03,2.02) 24 TOXSCL 13 Formaldehyde 24 Lognormal (4.60,3.70) 25 TOXSFL 13 Formaldehyde 24 Lognormal (4.60,3.70) 26 TOXRSL 13 Formaldehyde 24 Lognormal (3.60,2.70) 27 HARVLAL <sup>3, 6</sup> 7 Nitrogen Dioxide 24 Lognormal (10.70,0.42.50) 28 SOCLJANL <sup>5</sup> 8 Nitrogen Dioxide 24 Lognormal (10.70,0.42.50) 30 SOCLJANL <sup>5</sup> 8 Nitrogen Dioxide 24 Lognormal (10.70,0.42.50) 31 TXNETSCL 13 Inhalable Particles (PM10) 24 Lognormal (3.60,3.7.20) 33 TXNETSCL 13 Inhalable Particles (PM10) 24 Lognormal (3.60,3.7.20) 34 TXNETSCL 13 Inhalable Particles (PM10) 24 Lognormal (3.60,3.7.20) 35 PTEAMFL <sup>8</sup> 4 Inhalable Particles (PM10) 24 Lognormal (3.70,0.34.90) 36 TXNETSCL 13 Perchloroethylene 24 Lognormal (3.78,0.8) 37 TXNETSCL 13 Perchloroethylene 24 Lognormal (3.78,0.8) 38 TXNETSCL 13 Perchloroethylene 24 Lognormal (2.14,2.14) 39 TXNETSCL 13 Perchloroethylene 24 Lognormal (2.14,2.14)		WOODOUTL	1	Benzene	24	Lognormal (1.20,0.62)		
10   TM87S24L   2   Benzene   24   Lognormal (3.75,2.41)     11   PTM24L   4   Benzo(a)Pyrene   24   Lognormal (0.30,0.36)     12   TXNETALL   13   Chloroform   24   Lognormal (0.19,0.59)     13   TXNETSCL   13   Chloroform   24   Lognormal (0.18,0.16)     14   TXNETSFL   13   Chloroform   24   Lognormal (0.17,0.14)     15   TXNETRSL   13   Chloroform   24   Lognormal (0.21,0.86)     16   TM87B24L   2   Chloroform   24   Lognormal (0.21,0.86)     16   TM87B24L   2   Chloroform   24   Lognormal (0.24,0.80)     18   TM87S24L   2   Chloroform   24   Lognormal (0.49,0.80)     18   TM87S24L   2   Chloroform   24   Lognormal (0.79,1.36)     19   TXNETALL   13   Benzo(a)Pyrene   24   Lognormal (0.84,1.87)     20   TXNETSCL   13   Benzo(a)Pyrene   24   Lognormal (0.42,0.74)     21   TXNETSFL   13   Benzo(a)Pyrene   24   Lognormal (0.54,0.88)     22   TXNETRSL   13   Benzo(a)Pyrene   24   Lognormal (1.03,2.02)     23   TOXALL   13   Formaldehyde   24   Lognormal (4.60,3.70)     24   TOXSCL   13   Formaldehyde   24   Lognormal (4.60,3.70)     25   TOXSFL   13   Formaldehyde   24   Lognormal (3.60,2.70)     26   TOXRSL   13   Formaldehyde   24   Lognormal (3.60,2.70)     27   HARVLALa	8	TM87B24L	2	Benzene	24	Lognormal (5.10,3.46)		
TM87524L   2   Benzene   24   Lognormal (3.75,2.41)		TM87W24L	2	Benzene	24	Lognormal (6.41,3.83)		
11	10	TM87S24L	2	Benzene	24			
13   TXNETSCL   13   Chloroform   24   Lognormal (0.18,0.16)     14   TXNETSFL   13   Chloroform   24   Lognormal (0.17, 0.14)     15   TXNETRSL   13   Chloroform   24   Lognormal (0.21,0.86)     16   TM87B24L   2   Chloroform   24   Lognormal (0.64,1.11)     17   TM87W24L   2   Chloroform   24   Lognormal (0.49,0.80)     18   TM87S24L   2   Chloroform   24   Lognormal (0.79,1.36)     19   TXNETALL   13   Benzo(a)Pyrene   24   Lognormal (0.84,1.87)     20   TXNETSCL   13   Benzo(a)Pyrene   24   Lognormal (0.42,0.74)     21   TXNETSFL   13   Benzo(a)Pyrene   24   Lognormal (0.54,0.88)     22   TXNETRSL   13   Benzo(a)Pyrene   24   Lognormal (0.54,0.88)     22   TXNETRSL   13   Benzo(a)Pyrene   24   Lognormal (0.54,0.88)     22   TXNETRSL   13   Formaldehyde   24   Lognormal (4.00,3.20)     23   TOXALL   13   Formaldehyde   24   Lognormal (4.00,3.20)     24   TOXSCL   13   Formaldehyde   24   Lognormal (4.60,3.70)     25   TOXSFL   13   Formaldehyde   24   Lognormal (3.20,2.40)     26   TOXRSL   13   Formaldehyde   24   Lognormal (3.20,2.40)     27   HARVLAL®		PTM24L	4	Benzo(a)Pyrene	24			
14         TXNETSFL         13         Chloroform         24         Lognormal (0.17, 0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.21,0.86)           16         TM87B24L         2         Chloroform         24         Lognormal (0.49,0.80)           17         TM87W24L         2         Chloroform         24         Lognormal (0.49,0.80)           18         TM87S24L         2         Chloroform         24         Lognormal (0.79,1.36)           19         TXNETSLL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           23         TXNETRSL         13         Benzo(a)Pyrene         24	12	TXNETALL	13	Chloroform	24	Lognormal (0.19,0.59)		
14         TXNETSFL         13         Chloroform         24         Lognormal (0.17, 0.14)           15         TXNETRSL         13         Chloroform         24         Lognormal (0.21,0.86)           16         TM87B24L         2         Chloroform         24         Lognormal (0.64,1.11)           17         TM87W24L         2         Chloroform         24         Lognormal (0.49,0.80)           18         TM87S24L         2         Chloroform         24         Lognormal (0.79,1.36)           19         TXNETALL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSCL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSSL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSSL         13         Benzo(a)Pyrene         24         Lognormal (0.40,0.3.20)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (0.40,0.3.20)           23         TOXALL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           24         TXNETSSL         13         Benzo(a)Pyrene         24	13	TXNETSCL	13	Chloroform	24	Lognormal (0.18,0.16)		
TXNETRSL   13   Chloroform   24   Lognormal (0.21,0.86)	14	TXNETSFL	13	Chloroform	24			
17         TM87W24L         2         Chloroform         24         Lognormal (0.49,0.80)           18         TM87S24L         2         Chloroform         24         Lognormal (0.79,1.36)           19         TXNETALL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSCL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (3.60,2.70)           25         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           26         TOXRSL         13         Formaldehyde         24         Lognormal (7.20,0.39,30)           28         SOCLJANL <sup>b</sup> 8         Nitrogen Dioxide         24	15	TXNETRSL	13	Chloroform	24			
18         TM87S24L         2         Chloroform         24         Lognormal (0.79,1.36)           19         TXNETALL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSCL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLAL <sup>a,c</sup> 7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (77.00,42.50)           29         SOCLMARL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles	16	TM87B24L	2	Chloroform	24	Lognormal (0.64,1.11)		
18         TM87S24L         2         Chloroform         24         Lognormal (0.79,1.36)           19         TXNETALL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSCL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALBORD         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLBORD         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLBORD         8         Nitrogen Dioxide	17	TM87W24L	2	Chloroform	24	Lognormal (0.49,0.80)		
19         TXNETALL         13         Benzo(a)Pyrene         24         Lognormal (0.84,1.87)           20         TXNETSCL         13         Benzo(a)Pyrene         24         Lognormal (0.42,0.74)           21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLAL <sup>9,C</sup> 7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANL <sup>9</sup> 8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULL <sup>5</sup> 8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particle	18	TM87S24L	2	Chloroform	24			
21         TXNETSFL         13         Benzo(a)Pyrene         24         Lognormal (0.54,0.88)           22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALacc         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLb         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLb         8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULLb         8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSFL         13         Inhal	19	TXNETALL	13	Benzo(a)Pyrene	24			
22         TXNETRSL         13         Benzo(a)Pyrene         24         Lognormal (1.03,2.02)           23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (3.20,2.40)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.60,2.70)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALacc         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLb         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLb         8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULLb         8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSSL         13	20	TXNETSCL	13	Benzo(a)Pyrene	24	Lognormal (0.42,0.74)		
23         TOXALL         13         Formaldehyde         24         Lognormal (4.00,3.20)           24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALacc         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLbcccc         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLbccccc         8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULLbccccccc         8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL		1	13	Benzo(a)Pyrene	24	Lognormal (0.54,0.88)		
24         TOXSCL         13         Formaldehyde         24         Lognormal (4.60,3.70)           25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALacc         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLb         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLb         8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULLb         8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNET				Benzo(a)Pyrene	24	Lognormal (1.03,2.02)		
25         TOXSFL         13         Formaldehyde         24         Lognormal (3.20,2.40)           26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLALaccccccccccccccccccccccccccccccccccc				Formaldehyde	24	Lognormal (4.00,3.20)		
26         TOXRSL         13         Formaldehyde         24         Lognormal (3.60,2.70)           27         HARVLAL <sup>a,c</sup> 7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETSCL         13         Perchloroethylene         24         Lognormal (2.18,3.89)	~ <del>~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~</del>	<u> </u>			24	Lognormal (4.60,3.70)		
27         HARVLAL a.c.         7         Nitrogen Dioxide         24         Lognormal (72.00,39.30)           28         SOCLJANLb         8         Nitrogen Dioxide         24         Lognormal (107.00,42.50)           29         SOCLMARLb         8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULLb         8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFLa         4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (2.14,2.14)		1		· · · · · · · · · · · · · · · · · · ·	24	Lognormal (3.20,2.40)		
SOCLJANL    8		1			24	Lognormal (3.60,2.70)		
29         SOCLMARL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (53.70,22.60)           30         SOCLJULL <sup>b</sup> 8         Nitrogen Dioxide         24         Lognormal (77.20,34.20)           31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)		1	7	Nitrogen Dioxide	24	Lognormal (72.00,39.30)		
30   SOCLJULL <sup>b</sup>   8   Nitrogen Dioxide   24   Lognormal (77.20,34.20)     31   TXNETALL   13   Inhalable Particles (PM10)   24   Lognormal (38.60,34.60)     32   TXNETSCL   13   Inhalable Particles (PM10)   24   Lognormal (51.60,37.20)     33   TXNETSFL   13   Inhalable Particles (PM10)   24   Lognormal (30.70,24.80)     34   TXNETRSL   13   Inhalable Particles (PM10)   24   Lognormal (37.00,34.90)     35   PTEAMFL <sup>a</sup>   4   Inhalable Particles (PM10)   24   Lognormal (91.20,50.70)     36   TXNETALL   13   Perchloroethylene   24   Lognormal (2.18,3.89)     37   TXNETSCL   13   Perchloroethylene   24   Lognormal (3.78,7.08)     38   TXNETSFL   13   Perchloroethylene   24   Lognormal (2.14,2.14)     39   TXNETRSL   13   Perchloroethylene   24   Lognormal (1.40,1.65)		L	8	Nitrogen Dioxide	24	Lognormal (107.00,42.50)		
31         TXNETALL         13         Inhalable Particles (PM10)         24         Lognormal (38.60,34.60)           32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)		1	8	Nitrogen Dioxide	24	Lognormal (53.70,22.60)		
32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	30	SOCLJULL⁵	8	Nitrogen Dioxide	24	Lognormal (77.20,34.20)		
32         TXNETSCL         13         Inhalable Particles (PM10)         24         Lognormal (51.60,37.20)           33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	31	TXNETALL	13	Inhalable Particles (PM10)	24	Lognormal (38.60,34.60)		
33         TXNETSFL         13         Inhalable Particles (PM10)         24         Lognormal (30.70,24.80)           34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	32	TXNETSCL	13	Inhalable Particles (PM10)	24			
34         TXNETRSL         13         Inhalable Particles (PM10)         24         Lognormal (37.00,34.90)           35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	33	TXNETSFL	13	Inhalable Particles (PM10)	24			
35         PTEAMFL <sup>a</sup> 4         Inhalable Particles (PM10)         24         Lognormal (91.20,50.70)           36         TXNETALL         13         Perchloroethylene         24         Lognormal (2.18,3.89)           37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	34	TXNETRSL	13	Inhalable Particles (PM10)	24			
37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	35	PTEAMFL <sup>a</sup>	4	Inhalable Particles (PM10)	24			
37         TXNETSCL         13         Perchloroethylene         24         Lognormal (3.78,7.08)           38         TXNETSFL         13         Perchloroethylene         24         Lognormal (2.14,2.14)           39         TXNETRSL         13         Perchloroethylene         24         Lognormal (1.40,1.65)	36	TXNETALL	13	Perchloroethylene	24	· · · · · · · · · · · · · · · · · · ·		
38 TXNETSFL 13 Perchloroethylene 24 Lognormal (2.14,2.14) 39 TXNETRSL 13 Perchloroethylene 24 Lognormal (1.40,1.65)	37	TXNETSCL	13	Perchloroethylene				
39 TXNETRSL 13 Perchloroethylene 24 Lognormal (1.40,1.65)	38	TXNETSFL						
	39	TXNETRSL	13	Perchloroethylene				
	40	WOODOUTL	1	Perchloroethylene				

			Outdoors		
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type (Data
41	TM87B24L	2	Perchloroethylene	24	Lognormal (2.90,2.55)
42	TM87W24L	2	Perchloroethylene	24	Lognormal (4.06,3.08)
43	TM87S24L	2	Perchloroethylene	. 24	Lognormal (1.75,0.99)
44	TXNETALL	13	Trichloroethylene	24	Lognormal (0.87,2.02)
45	TXNETSCL	13	Trichloroethylene	24	Lognormal (0.96,1.07)
46	TXNETSFL	13	Trichloroethylene	24	Lognormal (1.01,3.98)
47	TXNETRSL	13	Trichloroethylene	24	Lognormal (0.70,1.39)
48	TM87B24L	2	Trichloroethylene	24	Lognormal (0.16,0.14)
49	TM87W24L	2	Trichloroethylene	24	Lognormal (0.21,0.18)
50	TM87S24L	2	Trichloroethylene	24 .	Lognormal (0.11,0.05)
51	CRIAQALL°	10	Benzene	24	Lognormal (8.63,7.99)
52	CRIAQPGL°	10	Benzene	24	Lognormal (5.43,3.20)
53	CRIAQSCL°	10	Benzene	24	Lognormal (15.02,11.18)
54	CRIAQSDL°	10	Benzene	24	Lognormal (6.07,2.56)
55	CRIAQALL°	10	Nitrogen Dioxide	24	Lognormal (43.30,32.00)
56	CRIAQPGL°	10	Nitrogen Dioxide	24	Lognormal (33.90,24.50)
57	CRIAQSCL°	10	Nitrogen Dioxide	24	Lognormal (65.80,41.40)
58	CRIAQSDL°	10	Nitrogen Dioxide	24	Lognormal (39.50,22.60)
59	CRIAQALL <sup>a,c</sup>	10	Carbon Monoxide	24	Lognormal (1.10,1.40)
60	CRIAQPGL°	10	Carbon Monoxide	24	Lognormai (0.80,0.60)
61	CRIAQSCL°	10	Carbon Monoxide	24	Lognormal (2.20,2.30)
62	CRIAQSDL°	10	Carbon Monoxide	24	Lognormal (0.80,0.60)
65	CABENZ97	30	Benzene	24	Lognormal (1.86,2.16)
66	CABENZ98	30	Benzene	24	Lognormal (1.87,1.97)
67	CABENZ99	30	Benzene	24	Lognormal (1.68,2.07)
- 68	CABENZ <sup>a</sup>	30	Benzene	24	Lognormal (1.82,2.08)
69	OABENZ97	30	Benzene	24	Lognormal (1.19,1.34)
70	OABENZ98	30	Benzene	24	Lognormal (1.17,1.08)
71	OABENZ99	30	Benzene	24	Lognormal (1.22,1.38)
72	OABENZ		Benzene	24	
73	SFBENZ97		Benzene		Lognormal (1.20,1.27)
74	SFBENZ98		Benzene	24	Lognormal (1.76,174)
75	SFBENZ99			24	Lognormal (1.87,1.75)
76	SFBENZ		Benzene	24	Lognormal (2.04,2.37)
			Benzene	24	Lognormal (1.84,1.82)
77	SCBENZ97		Benzene	24	Lognormal (2.63,2.13)
78 	SCBENZ98		Benzene	24	Lognormal (2.62,2.46)
79	SCBENZ99		Benzene	24	Lognormal (2.43,2.69)
80	SCBENZ	30	Benzene	24	Lognormal (2.59,2.43)

B-23

Case Number Number         Ref         Pollutant         Averaging Period         Distribution Type (Data)           81         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           82         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           83         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           84         CABAP97         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           35         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           86         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           88         OABAP9         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           93         SCBAP93         30         Benzo(a)pyrene <td< th=""><th></th><th></th><th></th><th>Outdoors</th><th></th><th></th></td<>				Outdoors		
81         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.15,0.30)           82         CABAP98         30         Benzo(a)pyrene         24         Lognormal (0.18,0.39)           83         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           34         CABAP3         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           35         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           37         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,16).30)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           93         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           93         SCBAP93         30         Benzo(a)pyrene         24<		Case Name	Ref	Pollutant		Distribution Type (Data)
83         CABAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.28)           84         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           35         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           86         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.21,0.65)           37         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           89         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.14,0.22)           93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.14,0.22)           94         SCBAP98         30         Benzo(a)pyrene         24 <td>81</td> <td>CABAP97</td> <td>30</td> <td>Benzo(a)pyrene</td> <td></td> <td>Lognormal (0.15,0.30)</td>	81	CABAP97	30	Benzo(a)pyrene		Lognormal (0.15,0.30)
84         CABAP³         30         Benzo(a)pyrene         24         Lognormal (0.16,0.32)           35         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           86         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           87         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           92         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           95         SCBAP99         30         Benzo(a)pyrene         24 <td>82</td> <td>CABAP98</td> <td>30</td> <td>Benzo(a)pyrene</td> <td>24</td> <td>Lognormal (0.18,0.39)</td>	82	CABAP98	30	Benzo(a)pyrene	24	Lognormal (0.18,0.39)
35         OABAP97         30         Benzo(a)pyrene         24         Lognormal (0.18,0.45)           86         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           37         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.10,0.50)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           91         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           93         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP9         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           97         CACHL97         30         Benzo(a)pyrene         24 <td>83</td> <td>CABAP99</td> <td>30</td> <td>Benzo(a)pyrene</td> <td>24</td> <td>Lognormal (0.14,0.28)</td>	83	CABAP99	30	Benzo(a)pyrene	24	Lognormal (0.14,0.28)
86         OABAP98         30         Benzo(a)pyrene         24         Lognormal (0.24,0.65)           87         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.10,0.20)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP9         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP9         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           95         SCBAP93         30         Benzo(a)pyrene         24	84	CABAPa	30	Benzo(a)pyrene	24	Lognormal (0.16,0.32)
37         OABAP99         30         Benzo(a)pyrene         24         Lognormal (0.17,0.42)           88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           95         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.14,0.25)           97         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           99         CACHL99         30         Chloroform         24         <	35	OABAP97	30	Benzo(a)pyrene	-24	Lognormal (0.18,0.45)
88         OABAP         30         Benzo(a)pyrene         24         Lognormal (0.20,0.50)           89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP9         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.14,0.25)           97         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           98         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL93         30         Chloroform         24         L	86	OABAP98	30	Benzo(a)pyrene	24	Lognormal (0.24,0.65)
89         SFBAP97         30         Benzo(a)pyrene         24         Lognormal (0.10,0.16)           90         SFBAP98         30         Benzo(a)pyrene         24         Lognormal (0.16,0.30)           91         SFBAP99         30         Benzo(a)pyrene         24         Lognormal (0.12,0.20)           92         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           97         CACHL97         30         Chloroform         24         Lognormal (0.14,0.25)           97         CACHL98         30         Chloroform         24         Lognormal (0.14,0.25)           99         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           100         CACHL98         30         Chloroform         24         Lo	87	OABAP99	30	Benzo(a)pyrene	24	Lognormal (0.17,0.42)
90 SFBAP98 30 Benzo(a)pyrene 24 Lognormal (0.16,0.30) 91 SFBAP99 30 Benzo(a)pyrene 24 Lognormal (0.12,0.20) 92 SFBAP 30 Benzo(a)pyrene 24 Lognormal (0.12,0.22) 93 SCBAP97 30 Benzo(a)pyrene 24 Lognormal (0.12,0.22) 94 SCBAP98 30 Benzo(a)pyrene 24 Lognormal (0.14,0.24) 95 SCBAP99 30 Benzo(a)pyrene 24 Lognormal (0.14,0.23) 96 SCBAP 30 Benzo(a)pyrene 24 Lognormal (0.14,0.23) 97 CACHL97 30 Chloroform 24 Lognormal (0.19,0.21) 98 CACHL98 30 Chloroform 24 Lognormal (0.15,0.15) 99 CACHL99 30 Chloroform 24 Lognormal (0.25,0.04) 100 CACHL9 30 Chloroform 24 Lognormal (0.20,0.19) 101 OACHL97 30 Chloroform 24 Lognormal (0.20,0.19) 102 OACHL98 30 Chloroform 24 Lognormal (0.29,0.14) 102 OACHL98 30 Chloroform 24 Lognormal (0.29,0.14) 103 OACHL99 30 Chloroform 24 Lognormal (0.25,0.03) 104 OACHL 30 Chloroform 24 Lognormal (0.25,0.03) 105 SFCHL99 30 Chloroform 24 Lognormal (0.27,0.09) 105 SFCHL97 30 Chloroform 24 Lognormal (0.27,0.09) 105 SFCHL98 30 Chloroform 24 Lognormal (0.27,0.09) 106 SFCHL98 30 Chloroform 24 Lognormal (0.27,0.09) 107 SFCHL99 30 Chloroform 24 Lognormal (0.09,0.08) 108 SFCHL 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.25,0.03) 1101 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.03) 1102 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.03) 1103 SFCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 111 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 112 SCCHL 30 Chloroform 24 Lognormal (0.25,0.04) 113 CAFORM97 30 Formaldehyde 24 Lognormal (0.25,0.04) 114 CAFORM98 30 Formaldehyde 24 Lognormal (5.29,4.60) 115 CAFORM99 30 Formaldehyde 24 Lognormal (5.29,4.60)	- 88	OABAP	30	Benzo(a)pyrene	24	Lognormal (0.20,0.50)
91 SFBAP99 30 Benzo(a)pyrene 24 Lognormal (0.12,0.20) 92 SFBAP 30 Benzo(a)pyrene 24 Lognormal (0.12,0.22) 93 SCBAP97 30 Benzo(a)pyrene 24 Lognormal (0.12,0.22) 94 SCBAP98 30 Benzo(a)pyrene 24 Lognormal (0.14,0.24) 95 SCBAP99 30 Benzo(a)pyrene 24 Lognormal (0.14,0.23) 96 SCBAP 30 Benzo(a)pyrene 24 Lognormal (0.14,0.23) 97 CACHL97 30 Chloroform 24 Lognormal (0.19,0.21) 98 CACHL98 30 Chloroform 24 Lognormal (0.15,0.15) 99 CACHL99 30 Chloroform 24 Lognormal (0.25,0.04) 100 CACHL <sup>a</sup> 30 Chloroform 24 Lognormal (0.25,0.04) 101 OACHL97 30 Chloroform 24 Lognormal (0.29,0.14) 102 OACHL98 30 Chloroform 24 Lognormal (0.29,0.14) 103 OACHL99 30 Chloroform 24 Lognormal (0.25,0.03) 104 OACHL 30 Chloroform 24 Lognormal (0.25,0.03) 105 SFCHL97 30 Chloroform 24 Lognormal (0.25,0.03) 106 SFCHL97 30 Chloroform 24 Lognormal (0.27,0.09) 107 SFCHL99 30 Chloroform 24 Lognormal (0.09,0.08) 108 SFCHL 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.25,0.03) 108 SFCHL 30 Chloroform 24 Lognormal (0.25,0.03) 109 SCCHL97 30 Chloroform 24 Lognormal (0.25,0.03) 109 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.03) 109 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.03) 109 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.03) 101 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.03) 102 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 107 SFCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 108 SFCHL 30 Chloroform 24 Lognormal (0.25,0.04) 110 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.04) 111 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 112 SCCHL 30 Chloroform 24 Lognormal (0.25,0.04) 113 CAFORM97 30 Formaldehyde 24 Lognormal (5.29,4.60) 114 CAFORM98 30 Formaldehyde 24 Lognormal (5.29,4.60) 115 CAFORM99 30 Formaldehyde 24 Lognormal (5.29,4.60)	89	SFBAP97	30	Benzo(a)pyrene	24	Lognormal (0.10,0.16)
92         SFBAP         30         Benzo(a)pyrene         24         Lognormal (0.12,0.22)           93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           98         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           99         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL3         30         Chloroform         24         Lognormal (0.29,0.14)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.03)           103         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0	90	SFBAP98	30	Benzo(a)pyrene	24	Lognormal (0.16,0.30)
93         SCBAP97         30         Benzo(a)pyrene         24         Lognormal (0.15,0.27)           94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           98         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           99         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL9         30         Chloroform         24         Lognormal (0.25,0.04)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.	91	SFBAP99	30	Benzo(a)pyrene	24	Lognormal (0.12,0.20)
94         SCBAP98         30         Benzo(a)pyrene         24         Lognormal (0.14,0.24)           95         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           98         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL9         30         Chloroform         24         Lognormal (0.20,0.19)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09	92	SFBAP	30	Benzo(a)pyrene	24	Lognormal (0.12,0.22)
95         SCBAP99         30         Benzo(a)pyrene         24         Lognormal (0.14,0.23)           96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           98         CACHL98         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL9         30         Chloroform         24         Lognormal (0.25,0.04)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL98         30         Chloroform         24         Lognormal (0.25,0.	93	SCBAP97	30	Benzo(a)pyrene	24	Lognormal (0.15,0.27)
96         SCBAP         30         Benzo(a)pyrene         24         Lognormal (0.14,0.25)           97         CACHL97         30         Chloroform         24         Lognormal (0.19,0.21)           98         CACHL98         30         Chloroform         24         Lognormal (0.15,0.15)           99         CACHL99         30         Chloroform         24         Lognormal (0.25,0.04)           100         CACHL8         30         Chloroform         24         Lognormal (0.20,0.19)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL9         30         Chloroform         24         Lognormal (0.25,0.03) </td <td>94</td> <td>SCBAP98</td> <td>30</td> <td>Benzo(a)pyrene</td> <td>24</td> <td>Lognormal (0.14,0.24)</td>	94	SCBAP98	30	Benzo(a)pyrene	24	Lognormal (0.14,0.24)
97 CACHL97 30 Chloroform 24 Lognormal (0.19,0.21) 98 CACHL98 30 Chloroform 24 Lognormal (0.15,0.15) 99 CACHL99 30 Chloroform 24 Lognormal (0.25,0.04) 100 CACHL <sup>a</sup> 30 Chloroform 24 Lognormal (0.20,0.19) 101 OACHL97 30 Chloroform 24 Lognormal (0.29,0.14) 102 OACHL98 30 Chloroform 24 Lognormal (0.25,0.03) 103 OACHL99 30 Chloroform 24 Lognormal (0.25,0.03) 104 OACHL 30 Chloroform 24 Lognormal (0.27,0.09) 105 SFCHL97 30 Chloroform 24 Lognormal (0.07,0.09) 106 SFCHL98 30 Chloroform 24 Lognormal (0.09,0.08) 107 SFCHL99 30 Chloroform 24 Lognormal (0.07,0.04) 108 SFCHL 30 Chloroform 24 Lognormal (0.07,0.04) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.02) 110 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.02) 111 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 112 SCCHL 30 Chloroform 24 Lognormal (0.25,0.04) 113 CAFORM97 30 Formaldehyde 24 Lognormal (0.25,0.04) 114 CAFORM98 30 Formaldehyde 24 Lognormal (5.22,4.83) 115 CAFORM99 30 Formaldehyde 24 Lognormal (5.29,4.60) 116 CAFORM <sup>a</sup> 30 Formaldehyde 24 Lognormal (5.13,4.60)	95	SCBAP99	30	Benzo(a)pyrene	24 .	Lognormal (0.14,0.23)
98 CACHL98 30 Chloroform 24 Lognormal (0.15,0.15) 99 CACHL99 30 Chloroform 24 Lognormal (0.25,0.04) 100 CACHL <sup>a</sup> 30 Chloroform 24 Lognormal (0.20,0.19) 101 OACHL97 30 Chloroform 24 Lognormal (0.29,0.14) 102 OACHL98 30 Chloroform 24 Lognormal (0.25,0.03) 103 OACHL99 30 Chloroform 24 Lognormal (0.25,0.03) 104 OACHL 30 Chloroform 24 Lognormal (0.27,0.09) 105 SFCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 106 SFCHL98 30 Chloroform 24 Lognormal (0.07,0.04) 107 SFCHL99 30 Chloroform 24 Lognormal (0.07,0.04) 108 SFCHL 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.25,0.02) 110 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.02) 111 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.04) 112 SCCHL 30 Chloroform 24 Lognormal (0.25,0.04) 113 CAFORM97 30 Formaldehyde 24 Lognormal (0.25,0.04) 114 CAFORM98 30 Formaldehyde 24 Lognormal (5.22,4.83) 115 CAFORM99 30 Formaldehyde 24 Lognormal (5.29,4.60) 116 CAFORM <sup>a</sup> 30 Formaldehyde 24 Lognormal (5.13,4.60)	96	SCBAP	30	Benzo(a)pyrene	24	Lognormal (0.14,0.25)
99 CACHL99 30 Chloroform 24 Lognormal (0.25,0.04) 100 CACHL <sup>a</sup> 30 Chloroform 24 Lognormal (0.20,0.19) 101 OACHL97 30 Chloroform 24 Lognormal (0.29,0.14) 102 OACHL98 30 Chloroform 24 Lognormal (0.25,0.03) 103 OACHL99 30 Chloroform 24 Lognormal (0.25,0.03) 104 OACHL 30 Chloroform 24 Lognormal (0.27,0.09) 105 SFCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 106 SFCHL98 30 Chloroform 24 Lognormal (0.09,0.08) 107 SFCHL99 30 Chloroform 24 Lognormal (0.07,0.04) 108 SFCHL 30 Chloroform 24 Lognormal (0.025,0.03) 109 SCCHL97 30 Chloroform 24 Lognormal (0.09,0.08) 109 SCCHL97 30 Chloroform 24 Lognormal (0.25,0.02) 110 SCCHL98 30 Chloroform 24 Lognormal (0.25,0.02) 111 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 111 SCCHL99 30 Chloroform 24 Lognormal (0.25,0.04) 112 SCCHL 30 Chloroform 24 Lognormal (0.25,0.04) 113 CAFORM97 30 Formaldehyde 24 Lognormal (4.85,4.31) 114 CAFORM98 30 Formaldehyde 24 Lognormal (5.22,4.83) 115 CAFORM99 30 Formaldehyde 24 Lognormal (5.29,4.60) 116 CAFORM <sup>a</sup> 30 Formaldehyde 24 Lognormal (5.29,4.60)	97	CACHL97	30	Chloroform	24	Lognormal (0.19,0.21)
100         CACHL <sup>a</sup> 30         Chloroform         24         Lognormal (0.20,0.19)           101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.27,0.09)           107         SFCHL99         30         Chloroform         24         Lognormal (0.09,0.08)           108         SFCHL         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.29,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.26,0.06)<	98	CACHL98	30	Chloroform	24	Lognormal (0.15,0.15)
101         OACHL97         30         Chloroform         24         Lognormal (0.29,0.14)           102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.25,0.04)	99	CACHL99	30	Chloroform	24	Lognormal (0.25,0.04)
102         OACHL98         30         Chloroform         24         Lognormal (0.25,0.03)           103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04) </td <td>100</td> <td>CACHL</td> <td>30</td> <td>Chloroform</td> <td>24</td> <td>Lognormal (0.20,0.19)</td>	100	CACHL	30	Chloroform	24	Lognormal (0.20,0.19)
103         OACHL99         30         Chloroform         24         Lognormal (0.25,0.03)           104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (0.25,0.04)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4	101	OACHL97	30	Chloroform	24	Lognormal (0.29,0.14)
104         OACHL         30         Chloroform         24         Lognormal (0.27,0.09)           105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.2	102	OACHL98	30	Chloroform	24	Lognormal (0.25,0.03)
105         SFCHL97         30         Chloroform         24         Lognormal (0.09,0.08)           106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORMa         30         Formaldehyde         24         Lognormal	103	OACHL99	30	Chloroform	24	Lognormal (0.25,0.03)
106         SFCHL98         30         Chloroform         24         Lognormal (0.07,0.04)           107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.13,4.60)           116         CAFORMa         30         Formaldehyde         24         Lognormal (5.13,4.60)	104	OACHL	30	Chloroform	24	Lognormal (0.27,0.09)
107         SFCHL99         30         Chloroform         24         Lognormal (0.25,0.03)           108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	105	SFCHL97	30	Chloroform	24	Lognormal (0.09,0.08)
108         SFCHL         30         Chloroform         24         Lognormal (0.09,0.08)           109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	106	SFCHL98	30	Chloroform	24	Lognormal (0.07,0.04)
109         SCCHL97         30         Chloroform         24         Lognormal (0.25,0.02)           110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	107	SFCHL99	30	Chloroform	24	Lognormal (0.25,0.03)
110         SCCHL98         30         Chloroform         24         Lognormal (0.25,0.04)           111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	108	SFCHL	30	Chloroform	24	Lognormal (0.09,0.08)
111         SCCHL99         30         Chloroform         24         Lognormal (0.26,0.06)           112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM³         30         Formaldehyde         24         Lognormal (5.13,4.60)	109	SCCHL97	30	Chloroform	24	Lognormal (0.25,0.02)
112         SCCHL         30         Chloroform         24         Lognormal (0.25,0.04)           113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	110	SCCHL98	30	Chloroform	24	Lognormal (0.25,0.04)
113         CAFORM97         30         Formaldehyde         24         Lognormal (4.85,4.31)           114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM³         30         Formaldehyde         24         Lognormal (5.13,4.60)	111	SCCHL99	30	Chloroform	24	Lognormal (0.26,0.06)
114         CAFORM98         30         Formaldehyde         24         Lognormal (5.22,4.83)           115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORM <sup>a</sup> 30         Formaldehyde         24         Lognormal (5.13,4.60)	112	SCCHL	30	Chloroform	24	Lognormal (0.25,0.04)
115         CAFORM99         30         Formaldehyde         24         Lognormal (5.29,4.60)           116         CAFORMa         30         Formaldehyde         24         Lognormal (5.13,4.60)	113	CAFORM97	30	Formaldehyde	24	
116 CAFORM <sup>a</sup> 30 Formaldehyde 24 Lognormal (5.13,4.60)	114	CAFORM98	30	Formaldehyde	24	Lognormal (5.22,4.83)
116 CAFORM <sup>a</sup> 30 Formaldehyde 24 Lognormal (5.13,4.60)	115	CAFORM99	30	Formaldehyde	24	Lognormal (5.29,4.60)
	116	CAFORM <sup>a</sup>	30	Formaldehyde	24	
	117	OAFORM97	30	Formaldehyde	24	Lognormal (5.03,5.16)

Case Number         Ref         Pollutant         Averaging Period         Distribution Type (Data)           118         OAFORM98         30         Formaldehyde         24         Lognormal (5.00,4.66)           119         OAFORM99         30         Formaldehyde         24         Lognormal (4.74,4.36)           120         OAFORM         30         Formaldehyde         24         Lognormal (2.34,1.44)           121         SFFORM98         30         Formaldehyde         24         Lognormal (2.30,1.81)           122         SFFORM99         30         Formaldehyde         24         Lognormal (2.40,1.76)           123         SFFORM99         30         Formaldehyde         24         Lognormal (2.61,2.07)           124         SFFORM         30         Formaldehyde         24         Lognormal (5.38,3.54)           126         SCFORM97         30         Formaldehyde         24         Lognormal (6.08,3.3.71)           127         SCFORM9         30         Formaldehyde         24         Lognormal (6.59,4.89)           128         SCFORM         30         Formaldehyde         24         Lognormal (6.06,4.41)           129         CATETR97         30         Perchloroethylene         24 </th <th colspan="7">Outdoors</th>	Outdoors						
118         OAFORM98         30         Formaldehyde         24         Lognormal (5.00,4.66)           119         OAFORM9         30         Formaldehyde         24         Lognormal (4.19,3.32)           120         OAFORM         30         Formaldehyde         24         Lognormal (2.34,1.44)           121         SFFORM97         30         Formaldehyde         24         Lognormal (2.30,1.81)           122         SFFORM98         30         Formaldehyde         24         Lognormal (2.61,2.07)           124         SFFORM99         30         Formaldehyde         24         Lognormal (2.61,2.07)           125         SCFORM93         30         Formaldehyde         24         Lognormal (2.61,2.07)           126         SCFORM93         30         Formaldehyde         24         Lognormal (5.80,3.27)           127         SCFORM9         30         Formaldehyde         24         Lognormal (6.59,4.89)           128         SCFORM         30         Formaldehyde         24         Lognormal (6.06,4.41)           129         CATETR97         30         Perchloroethylene         24         Lognormal (0.76,0.96)           130         CATETR98         30         Perchloroethylene         <		Case Name	Ref	Pollutant		Distribution Type (Data)	
120	118	OAFORM98	30	Formaldehyde		Lognormal (5.00,4.66)	
121	119	OAFORM99	30	Formaldehyde	24	Lognormal (4.19,3.32)	
122   SFFORM98   30   Formaldehyde   24   Lognormal (2.30,1.81)   123   SFFORM99   30   Formaldehyde   24   Lognormal (2.30,1.81)   124   SFFORM   30   Formaldehyde   24   Lognormal (2.40,1.76)   125   SCFORM97   30   Formaldehyde   24   Lognormal (5.38,3.54)   126   SCFORM98   30   Formaldehyde   24   Lognormal (5.59,4.89)   127   SCFORM99   30   Formaldehyde   24   Lognormal (6.59,4.89)   128   SCFORM   30   Formaldehyde   24   Lognormal (6.66,4.41)   129   CATETR97   30   Perchloroethylene   24   Lognormal (0.78,0.96)   130   CATETR98   30   Perchloroethylene   24   Lognormal (0.70,0.86)   131   CATETR99   30   Perchloroethylene   24   Lognormal (0.74,0.88)   132   CATETR9   30   Perchloroethylene   24   Lognormal (0.74,0.88)   133   OATETR99   30   Perchloroethylene   24   Lognormal (0.46,0.24)   134   OATETR98   30   Perchloroethylene   24   Lognormal (0.46,0.24)   135   OATETR99   30   Perchloroethylene   24   Lognormal (0.42,0.18)   135   OATETR99   30   Perchloroethylene   24   Lognormal (0.43,0.26)   136   OATETR9   30   Perchloroethylene   24   Lognormal (0.45,0.23)   137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.45,0.23)   138   SFTETR99   30   Perchloroethylene   24   Lognormal (0.65,0.93)   139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   141   SCTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   142   SCTETR98   30   Perchloroethylene   24   Lognormal (0.67,0.91)   143   SCTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   144   SCTETR9   30   Perchloroethylene   24   Lognormal (0.67,0.91)   145   SCTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   145   SCTETR98   30   Perchloroethylene   24   Lognormal (0.67,0.91)   146   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC99   30   Trichloroethylene   24   Lognormal (0.27,0.09)   147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   150   OATRIC99   30   Trich	120	OAFORM	30	Formaldehyde	24	Lognormal (4.74,4.36)	
123	121	SFFORM97	30	Formaldehyde	24	Lognormal (2.34,1.44)	
124	122	SFFORM98	30	Formaldehyde	24	Lognormal (2.30,1.81)	
125   SCFORM97   30   Formaldehyde   24   Lognormal (5.38,3.54)   126   SCFORM98   30   Formaldehyde   24   Lognormal (5.80,3.27)   127   SCFORM99   30   Formaldehyde   24   Lognormal (6.59,4.89)   128   SCFORM   30   Formaldehyde   24   Lognormal (6.59,4.89)   129   CATETR97   30   Perchloroethylene   24   Lognormal (0.78,0.96)   130   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)   131   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)   132   CATETR8   30   Perchloroethylene   24   Lognormal (0.74,0.88)   133   OATETR97   30   Perchloroethylene   24   Lognormal (0.74,0.88)   134   OATETR98   30   Perchloroethylene   24   Lognormal (0.74,0.88)   135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.24)   134   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)   136   OATETR   30   Perchloroethylene   24   Lognormal (0.48,0.26)   137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.45,0.23)   137   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)   139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)   141   SCTETR97   30   Perchloroethylene   24   Lognormal (0.67,0.91)   142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.66,1.75)   142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.66,1.75)   143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.69,1.59)   144   SCTETR   30   Perchloroethylene   24   Lognormal (1.69,1.68)   145   CATRIC97   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)   147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   150   OATRIC98   30   Trichloroethylene   24   Lognormal (0.28,0.04)   151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   152   OATRIC	123	SFFORM99	30	Formaldehyde	24	Lognormal (2.61,2.07)	
126	124	SFFORM	30	Formaldehyde	24	Lognormal (2.40,1.76)	
127   SCFORM99   30   Formaldehyde   24   Lognormal (6.59,4.89)   128   SCFORM   30   Formaldehyde   24   Lognormal (6.06,4.41)   129   CATETR97   30   Perchloroethylene   24   Lognormal (0.76,0.96)   130   CATETR98   30   Perchloroethylene   24   Lognormal (0.70,0.86)   131   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)   132   CATETR8   30   Perchloroethylene   24   Lognormal (0.74,0.88)   133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)   134   OATETR98   30   Perchloroethylene   24   Lognormal (0.48,0.26)   135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)   136   OATETR9   30   Perchloroethylene   24   Lognormal (0.48,0.26)   137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.45,0.23)   137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.65,0.93)   138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)   139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   141   SCTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)   142   SCTETR98   30   Perchloroethylene   24   Lognormal (0.67,0.91)   143   SCTETR98   30   Perchloroethylene   24   Lognormal (1.66,1.75)   142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.68,1.75)   143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.69,1.75)   144   SCTETR99   30   Perchloroethylene   24   Lognormal (1.49,1.68)   145   CATRIC97   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)   146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)   148   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)   149   OATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.16)   149   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   150   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)   152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)   1	125	SCFORM97	30	Formaldehyde	24	Lognormal (5.38,3.54)	
128   SCFORM   30   Formaldehyde   24   Lognormal (6.06,4.41)     129   CATETR97   30   Perchloroethylene   24   Lognormal (0.78,0.96)     130   CATETR98   30   Perchloroethylene   24   Lognormal (0.70,0.86)     131   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)     132   CATETR8   30   Perchloroethylene   24   Lognormal (0.74,0.88)     133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)     134   OATETR98   30   Perchloroethylene   24   Lognormal (0.42,0.18)     135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)     136   OATETR   30   Perchloroethylene   24   Lognormal (0.45,0.23)     137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.45,0.23)     138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.75,1.10)     138   SFTETR99   30   Perchloroethylene   24   Lognormal (0.65,0.93)     140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)     141   SCTETR97   30   Perchloroethylene   24   Lognormal (0.67,0.91)     142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.66,1.75)     143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.33,1.61)     144   SCTETR99   30   Perchloroethylene   24   Lognormal (1.33,1.61)     145   CATRIC97   30   Perchloroethylene   24   Lognormal (1.30,0.15)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)     148   CATRIC9   30   Trichloroethylene   24   Lognormal (0.28,0.04)     150   OATRIC98   30   Trichloroethylene   24   Lognormal (0.28,0.04)     151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)     152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97	126	SCFORM98	30	Formaldehyde	24	Normal (5.80,3.27)	
129   CATETR97   30   Perchloroethylene   24   Lognormal (0.78,0.96)     130   CATETR98   30   Perchloroethylene   24   Lognormal (0.70,0.86)     131   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)     132   CATETR*   30   Perchloroethylene   24   Lognormal (0.74,0.88)     133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)     134   OATETR98   30   Perchloroethylene   24   Lognormal (0.42,0.18)     135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)     136   OATETR   30   Perchloroethylene   24   Lognormal (0.45,0.23)     137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.75,1.10)     138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)     139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.43,0.18)     140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)     141   SCTETR97   30   Perchloroethylene   24   Lognormal (0.67,0.91)     142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.66,1.75)     143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.33,1.61)     144   SCTETR9   30   Perchloroethylene   24   Lognormal (1.49,1.59)     145   CATRIC97   30   Trichloroethylene   24   Lognormal (1.49,1.59)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     146   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)     148   CATRIC*   30   Trichloroethylene   24   Lognormal (0.30,0.15)     149   OATRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     150   OATRIC98   30   Trichloroethylene   24   Lognormal (0.28,0.04)     151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)     152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.29,0.17)	127	SCFORM99	30	Formaldehyde	24	Lognormal (6.59,4.89)	
130   CATETR98   30   Perchloroethylene   24   Lognormal (0.70,0.86)     131   CATETR99   30   Perchloroethylene   24   Lognormal (0.76,0.68)     132   CATETR3   30   Perchloroethylene   24   Lognormal (0.74,0.88)     133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)     134   OATETR98   30   Perchloroethylene   24   Lognormal (0.42,0.18)     135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)     136   OATETR   30   Perchloroethylene   24   Lognormal (0.45,0.23)     137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.45,0.23)     138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)     139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.65,0.93)     140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)     141   SCTETR97   30   Perchloroethylene   24   Lognormal (1.66,1.75)     142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.33,1.61)     143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.49,1.59)     144   SCTETR   30   Perchloroethylene   24   Lognormal (1.49,1.59)     145   CATRIC97   30   Trichloroethylene   24   Lognormal (0.30,0.15)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.15)     148   CATRIC9   30   Trichloroethylene   24   Lognormal (0.30,0.13)     149   OATRIC97   30   Trichloroethylene   24   Lognormal (0.27,0.09)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)     150   OATRIC98   30   Trichloroethylene   24   Lognormal (0.28,0.04)     151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)     152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.29,0.17)	128	SCFORM	30	Formaldehyde	24	Lognormal (6.06,4.41)	
131         CATETR99         30         Perchloroethylene         24         Lognormal (0.76,0.68)           132         CATETR³         30         Perchloroethylene         24         Lognormal (0.74,0.88)           133         OATETR97         30         Perchloroethylene         24         Lognormal (0.46,0.24)           134         OATETR98         30         Perchloroethylene         24         Lognormal (0.42,0.18)           135         OATETR99         30         Perchloroethylene         24         Lognormal (0.48,0.26)           136         OATETR         30         Perchloroethylene         24         Lognormal (0.45,0.23)           137         SFTETR97         30         Perchloroethylene         24         Lognormal (0.75,1.10)           138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR93         30         Perchloroethylene         24         Lognormal (0.67,0.91)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR93 <td< td=""><td>129</td><td>CATETR97</td><td>30</td><td>Perchloroethylene</td><td>24</td><td>Lognormal (0.78,0.96)</td></td<>	129	CATETR97	30	Perchloroethylene	24	Lognormal (0.78,0.96)	
132   CATETRa   30   Perchloroethylene   24   Lognormal (0.74,0.88)     133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)     134   OATETR98   30   Perchloroethylene   24   Lognormal (0.42,0.18)     135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)     136   OATETR   30   Perchloroethylene   24   Lognormal (0.45,0.23)     137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.75,1.10)     138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)     139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.43,0.18)     140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)     141   SCTETR97   30   Perchloroethylene   24   Lognormal (1.66,1.75)     142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.33,1.61)     143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.49,1.59)     144   SCTETR   30   Perchloroethylene   24   Lognormal (1.49,1.59)     145   CATRIC97   30   Trichloroethylene   24   Lognormal (0.30,0.15)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.30,0.13)     148   CATRICª   30   Trichloroethylene   24   Lognormal (0.30,0.13)     149   OATRICª   30   Trichloroethylene   24   Lognormal (0.28,0.04)     150   OATRICØ9   30   Trichloroethylene   24   Lognormal (0.28,0.04)     151   OATRICØ9   30   Trichloroethylene   24   Lognormal (0.28,0.04)     152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRICØ7   30   Trichloroethylene   24   Lognormal (0.29,0.17)	130	CATETR98	30	Perchloroethylene	24	Lognormal (0.70,0.86)	
132   CATETR <sup>a</sup>   30   Perchloroethylene   24   Lognormal (0.74,0.88)     133   OATETR97   30   Perchloroethylene   24   Lognormal (0.46,0.24)     134   OATETR98   30   Perchloroethylene   24   Lognormal (0.42,0.18)     135   OATETR99   30   Perchloroethylene   24   Lognormal (0.48,0.26)     136   OATETR   30   Perchloroethylene   24   Lognormal (0.45,0.23)     137   SFTETR97   30   Perchloroethylene   24   Lognormal (0.75,1.10)     138   SFTETR98   30   Perchloroethylene   24   Lognormal (0.65,0.93)     139   SFTETR99   30   Perchloroethylene   24   Lognormal (0.67,0.91)     140   SFTETR   30   Perchloroethylene   24   Lognormal (0.67,0.91)     141   SCTETR97   30   Perchloroethylene   24   Lognormal (1.66,1.75)     142   SCTETR98   30   Perchloroethylene   24   Lognormal (1.33,1.61)     143   SCTETR99   30   Perchloroethylene   24   Lognormal (1.49,1.59)     144   SCTETR   30   Perchloroethylene   24   Lognormal (1.49,1.68)     145   CATRIC97   30   Trichloroethylene   24   Lognormal (0.30,0.15)     146   CATRIC98   30   Trichloroethylene   24   Lognormal (0.30,0.15)     147   CATRIC99   30   Trichloroethylene   24   Lognormal (0.33,0.16)     148   CATRIC9   30   Trichloroethylene   24   Lognormal (0.30,0.13)     149   OATRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     150   OATRIC98   30   Trichloroethylene   24   Lognormal (0.28,0.04)     151   OATRIC99   30   Trichloroethylene   24   Lognormal (0.28,0.04)     152   OATRIC   30   Trichloroethylene   24   Lognormal (0.28,0.04)     153   SFTRIC97   30   Trichloroethylene   24   Lognormal (0.28,0.04)     154   Tr	131	CATETR99	30	Perchloroethylene	24	Lognormal (0.76,0.68)	
134	132	CATETR <sup>a</sup>	30	Perchloroethylene	24		
134         OATETR98         30         Perchloroethylene         24         Lognormal (0.42,0.18)           135         OATETR99         30         Perchloroethylene         24         Lognormal (0.48,0.26)           136         OATETR         30         Perchloroethylene         24         Lognormal (0.45,0.23)           137         SFTETR97         30         Perchloroethylene         24         Lognormal (0.65,0.93)           138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30	133	OATETR97	30	Perchloroethylene	24	Lognormal (0.46,0.24)	
135         OATETR99         30         Perchloroethylene         24         Lognormal (0.48,0.26)           136         OATETR         30         Perchloroethylene         24         Lognormal (0.45,0.23)           137         SFTETR97         30         Perchloroethylene         24         Lognormal (0.75,1.10)           138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (0.30,0.15)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30	134	OATETR98	30	Perchloroethylene	24		
136         OATETR         30         Perchloroethylene         24         Lognormal (0.45,0.23)           137         SFTETR97         30         Perchloroethylene         24         Lognormal (0.75,1.10)           138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR98         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (0.30,0.15)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC98         30         Trichloroethylene         24         Lognormal (0.23,0.13)           148         CATRIC97         30	135	OATETR99	30	Perchloroethylene	24		
137         SFTETR97         30         Perchloroethylene         24         Lognormal (0.75,1.10)           138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (0.30,0.15)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC98         30         Trichloroethylene         24         Lognormal (0.23,0.13)           148         CATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98		OATETR	30	Perchloroethylene	24	Lognormal (0.45,0.23)	
138         SFTETR98         30         Perchloroethylene         24         Lognormal (0.65,0.93)           139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.30,0.13)           148         CATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98	137	SFTETR97	30	Perchloroethylene	24		
139         SFTETR99         30         Perchloroethylene         24         Lognormal (0.43,0.18)           140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC3         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30<	138	SFTETR98	30	Perchloroethylene	24	, · · · · · · · · · · · · · · · · · · ·	
140         SFTETR         30         Perchloroethylene         24         Lognormal (0.67,0.91)           141         SCTETR97         30         Perchloroethylene         24         Lognormal (1.66,1.75)           142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC3         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30 <td>139</td> <td>SFTETR99</td> <td>30</td> <td>Perchloroethylene</td> <td>24</td> <td></td>	139	SFTETR99	30	Perchloroethylene	24		
142         SCTETR98         30         Perchloroethylene         24         Lognormal (1.33,1.61)           143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30<	140	SFTETR	30	Perchloroethylene	24		
143         SCTETR99         30         Perchloroethylene         24         Lognormal (1.49,1.59)           144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	141	SCTETR97	30	Perchloroethylene	24	Lognormal (1.66,1.75)	
144         SCTETR         30         Perchloroethylene         24         Lognormal (1.49,1.68)           145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	142	SCTETR98	30	Perchloroethylene	24	Lognormal (1.33,1.61)	
145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)			30	Perchloroethylene	24	Lognormal (1.49,1.59)	
145         CATRIC97         30         Trichloroethylene         24         Lognormal (0.30,0.15)           146         CATRIC98         30         Trichloroethylene         24         Lognormal (0.27,0.09)           147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	144	SCTETR	30	Perchloroethylene	24	Lognormal (1.49,1.68)	
147         CATRIC99         30         Trichloroethylene         24         Lognormal (0.33,0.16)           148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	145	CATRIC97	30	Trichloroethylene	24		
148         CATRIC³         30         Trichloroethylene         24         Lognormal (0.30,0.13)           149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	146	CATRIC98	30	Trichloroethylene	24	Lognormal (0.27,0.09)	
149         OATRIC97         30         Trichloroethylene         24         Lognormal (0.28,0.04)           150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	147	CATRIC99	30	Trichloroethylene	24	Lognormal (0.33,0.16)	
150         OATRIC98         30         Trichloroethylene         24         Lognormal (0.28,0.04)           151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)	148	CATRIC	30	Trichloroethylene	24	Lognormal (0.30,0.13)	
151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)		OATRIC97	30	Trichloroethylene	24	1	
151         OATRIC99         30         Trichloroethylene         24         Lognormal (0.27,0.03)           152         OATRIC         30         Trichloroethylene         24         Lognormal (0.28,0.04)           153         SFTRIC97         30         Trichloroethylene         24         Lognormal (0.29,0.17)		OATRIC98	30	Trichloroethylene	24	Lognormal (0.28,0.04)	
152 OATRIC 30 Trichloroethylene 24 Lognormal (0.28,0.04) 153 SFTRIC97 30 Trichloroethylene 24 Lognormal (0.29,0.17)		OATRIC99	30	Trichloroethylene	24	<u> </u>	
153 SFTRIC97 30 Trichloroethylene 24 Lognormal (0.29,0.17)			30	Trichloroethylene	24		
154 SFTRIC98 30 Trichloroethylene 24 Lognormal (0.24,0.06)	1	SFTRIC97	30	Trichloroethylene	24	Lognormal (0.29,0.17)	
	154	SFTRIC98	30	Trichloroethylene	24	Lognormal (0.24,0.06)	

Outdoors						
Case Number	Case Name	Ref	Pollutant	Averaging Period	Distribution Type (Data)	
155	SFTRIC99	30	Trichloroethylene	24	Lognormal (0.27,0.00)	
156	SFTRIC	30	Trichloroethylene	24	Lognormal (0.27,0.11)	
157	SCTRIC97	30	Trichloroethylene	24	Lognormal (0.40,0.24)	
158	SCTRIC98	30	Trichloroethylene	24	Lognormal (0.36,0.19)	
159	SCTRIC99	30	Trichloroethylene	24	Lognormal (0.45,0.39)	
160	SCTRIC	30	Trichloroethylene	24	Lognormal (0.40,0.27)	

<sup>&</sup>lt;sup>a</sup> Indicates case marked as default. See Table B-16a for recommended weights for default cases.

Table B-16a. Recommended Weights (in Percents) for Default Cases for Outdoors (Level3)

,	24-Hour	***************************************
N A Committee of the Co	Case Name (#)	Weight
Benzene	CABENZ (68)	100
Benzo(a)pyrene	CABAP (84)	100
Carbon Monoxide	CRIAQALL (59)	100
Chloroform	CACHL (100)	100
Formaldehyde	CAFORM (116)	100
Nitrogen Dioxide	HARVLAL (27)	100
PM10	PTEAMFL (35)	100
Perchloroethylene (Tetrachloroethylene)	CATETR (132)	100
Trichloroethylene	CATRIC (148)	100

<sup>&</sup>lt;sup>b</sup> Data for these cases are based on week-long measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.

<sup>&</sup>lt;sup>c</sup> Data for these cases are based on 48-hour measurements. Although they are included among model inputs for the 24-hour averaging period, they are best treated as "practice" data sets.

## References for Tables in Appendix B

- Sneldon, L., Clayton, A., Jones, B., Keever, J., Perritt, R., Smith, D., Whitaker, D., and Whitmore, R. 1992. *Indoor Pollutant Concentrations and Exposures*. Prepared for California Air Resources Board under Contract No. A833-156. Research Triangle Institute, Research Triangle Park, NC.
- 2. Wallace, C., Nelson, W., Ziegenfus, R., Pellizzari, E., Michael, L., Whitmore, R., Zelon, H., Hartwell, T., Perritt, R., and Westerdahl, D. 1991. AThe Los Angeles TEAM study: personal exposures, indoor-outdoor air concentrations, and breath concentrations of 25 volatile organic compounds. *Journal of Exposure Analysis and Environmental Epidemiology*, 1:157-192.
- 3. Wallace, L.A. 1987. The Total Exposure Assessment Methodology (TEAM) Study: Summary and Analysis, Volume 1. Report No. EPA/600/6-87-002a, U.S. Environmental Protection Agency, Washington, DC.
- Sheldon, L., Clayton, A., Keever, J., Perritt, R., and Whitaker, D. 1992. PTEAM: Monitoring of Phthalates and PAHs in Indoor and Outdoor Air Samples in Riverside, California. Prepared for California Air Resources Board under Contract No. A933-144. Research Triangle Institute, Research Triangle Park, NC.
- 5a. Sexton, K., Petreas, M.X., and Liu, K.-S. 1989. "Formaldehyde exposure inside mobile homes." *Environmental Science and Technology*, 23: 985-988.
- 5b. Sexton, K., Liu, K.-S., and Petreas, M.X. 1986. "Formaldehyde concentrations inside private residences: a mail-out approach to indoor air monitoring." *Journal of the Air Pollution Control Association*, 36: 698-704.
- Rogozen, M.B., Maldonado, G., Grosjean, D., Shochet, A., and Rapoport, R. 1984
   *Formaldehyde: A Survey of Airborne Concentrations and Sources*. Report No. SAI 84/1642, prepared for California Air Resources Board under Contract No. A2-059N-32.
   Science Applications, Inc., Hermosa Beach, CA.
- 7. Spengler, J.D., Ryan, P.B., and Schwab, M. 1992. *Nitrogen Dioxide Exposure Studies--Volume 4, Personal Exposure to Nitrogen Dioxide in the Los Angeles Basin*. Report No. GRI-92/0426, Gas Research Institute, Chicago, IL.
- 8. Wilson, A.L., Colome, S.D., Baker, P.E., and Becker, E.W. 1986. Residential Indoor Air Quality Characterization Study of Nitrogen Dioxide, Phase I, Volume 2: Final Report. Prepared for Southern California Gas Company, Los Angeles, CA.
- Colome, S.D., Kado, N.Y., Jacques, P., and Kleinman, M. 1990. "Indoor-outdoor relationships of particles less than 10 Φm in aerodynamic diameter (PM<sub>10</sub>) in homes of asthmatics." Proceedings of the 5th International Conference on Indoor Air Quality and Climate, Toronto, Canada, Vol. 2, pp. 275-280.
- 10. Wilson, A.L., Colome, S.D., and Tian, Y. 1993. California Residential Indoor Air Quality Study, Volume 1: Methodology and Descriptive Statistics. Prepared for Gas Research Institute, Pacific Gas and Electric Company, San Diego Gas and Electric Company, and Southern California Gas Company by Integrated Environmental Services, Irvine, CA.

- 11. Turk, B.H., Brown, J.T., Geisling-Sobotka, K., Froehlich, D.A., Grimsrud. D.T., Harrison, J., and Revzan, K.L. 1986. "Indoor air quality measurements in 38 Pacific Northwest commercial buildings." *Proceedings of the 79th Annual Meeting of the Air Pollution Control Association*, Pittsburgh, PA.
- 12. Shikiya, D.C., Liu, C.S., Kahn, M.I., Juarros, J., and Barcikowski, W. 1989. *In-Vehicle Characterization Study in the South Coast Air Basin*. South Coast Air Quality Management District, Diamond Bar, CA.
- 13. ARB. 1988. Air Toxics Monitoring in the State of California. State of California, Air Resources Board, Sacramento, CA.
- 14. Unpublished data calculated from a database received from the Gas Research Institute, Chicago, IL.
- 15. Billick, I.H. 1988. "Simulation of indoor nitrogen dioxide concentrations." Transactions of an International Specialty Conference, *Combustion Processes and the Quality of the Indoor Environment*, Niagara Falls, N.Y., pp. 151-172.
- 16. MWD. 1991. *Urban Water Use Characteristics in the Metropolitan Water District of Southern California*. Draft document dated August 1991.
- 17. Koontz, M.D., Mehegan, L.L., and Nagda, N.L. 1992. *Distribution and Use of Cooking Appliances That Can Affect Indoor Air Quality*. Report No. GRI-93/0013, Gas Research Institute, Chicago, IL.
- 18. Traynor, G.T., Aceti, J.C., Apte, M.G., Smith, B.V., Green, L.L., Smith-Reiser, A., Novak, K.M., and Moses, D.O. 1989. *Macromodel for Assessing Residential Concentrations of Combustion-Generated Pollutants: Model Development and Preliminary Predictions for CO, NO<sub>2</sub>, and Respirable Suspended Particles. Report No. LBL-25211, Lawrence Berkeley Laboratory, Berkeley, CA.*
- Spicer, C.W., Coutant, R.W., Ward, G.F., Joseph, D.W., Gaynor, A.J., and Billick, I.H. 1989. "Rates and mechanisms of NO<sub>2</sub> removal from indoor air by residential materials." Environment International, 15:643-654.
- 20. Calculated from a database of PFT measurements, as described in *Database of PFT Ventilation Measurements: Description and User=s Manual*. Report prepared for the U.S. Environmental Protection Agency under Contract No. 68-02-4254, Versar, Inc., Springfield, VA.
- 21. ADM Associates. 1990. Pilot Residential Air Exchange Survey, Task 2: Pilot Infiltration Study, Indoor Air Quality Assessment Project. Report prepared for the California Energy Commission under Contract No. 400-88-020. ADM Associates, Inc., Sacramento, CA.
- 22. Avol, Edward L., Navidi, William C., and Colome, Steven D. Modeling Ozone Levels in and around Southern California Homes. *Environmental Science & Technology*, FEB 15 1998, v 32 n 4, p 463+.
- 23. Colome, S.D., Fung, K., Behrens, D.W., Billick I.H., Tian, Y., and Wilson A.L. 1994. Benzene and toluene concentrations inside and outside of homes in California. Presented at the Air and Waste Management Association 87<sup>th</sup> Annual Meeting and Exhibition. Cincinnati, OH. 94-WP90.03.

- 24. Offermann, F. J.; S.A. Loiselle; J.M. Daisey; L.A. Gundel; and A.T. Hodgson. 1990. "A Pilot Study to Measure Indoor Concentrations of Polycyclic Aromatic Compounds." In: Indoor Air '90, Proceedings of the International Conference in Indoor Air Quality and Climate, Ottawa, Canada, 2: 379-384.
- 25. Peters, J.M. 1997, Epidemiological Investigation to Identify Chronic Health Effects of Ambient Air Pollutants on Southern California. USC-LA, Final Report to CARB, NTIS No. PB 98-140833/XAB
- 26. Daisey, J.M.; Hodgson, A.T.; Fisk, W.J.; Mendell, M.J.; Brinke, J.T. Volatile Organic Compounds in Twelve California Office Buildings: Classes, Concentrations and Sources, Report Number: LBL-33686 1993. *Atmospheric Environment*, Vol. 28, No. 22, pp. 3557-3562, 1994
- 27. Womble, S.E., Girman, J.R., Ronca, E.L., Brightman, H.S., and McCarthy, J.F. (1995). "Developing Baseline Information on Buildings and Indoor Air Quality (BASE '94): Part I-Study Design, Building Selection, and Building Descriptions." Proceedings of Healthy Buildings '95 Milan, Italy, Vol. 3, 1995, pp. 1305-1310.
- 28. Underwood, M.C., 1996, Assessing the indoor air impact from a hazardous waste site: A case study. *Toxicology and Industrial Health*, 12: 179-188.
- 29. Rodes, C., L. Sheldon, D. Whitaker, A. Clayton, K, Fitzgerald, J. Flanagan, F. DiGenova, S. Hering, and C. Frazier. 1998. *Measuring Concentrations of Selected Air Pollutants Inside California Vehicles*. Prepared for the California Air Resources Board, Contract No, 95-339.
- 30. US EPA. Air Toxics Data Archive, Merged Data Set (contains California ambient concentrations from the ARB Toxics Monitoring Network, The Bay Area Air Quality Management District Air Toxics Monitoring Network, and the South Coast Air Quality Management District Air Toxics Monitoring Network).
- 31. Lewis, C.W. 1991. Sources of air pollutants indoor: VOC and fine particulate species. Journal of Exposure Analysis and Environmental Epidemiology 1(1) 31-44.
- 32. Spicer, C.W., Kenny, D.V., Ward, G.F., and Billick, I.H., 1993, *Journal of the Air & Waste Management Association*, v 43 n 11, p1479+.
- 33. Colombo, A., De Bortoli, M., Knoppel, H., Pecchio, E., and Vissers, H. 1993. Adsorption of selected volatile organic compounds on a carpet, a wall coating, and a gypsum board in a test chamber. *Indoor Air* 3:276-282.
- 34. Ligocki, M.P., L.G. Salmon, T. Fall, M.C. Jones, W.W. Nazaroff and G.R. Cass. 1993. Characteristics of airborne particles inside Southern California museums. *Atmos. Environ.* 27A(5):697-711.
- 35. Wilson, A.L., S.D.Colome, Y.Tian, E.W.Becker, P.E.Baker, D.W.Behrens, I.H. Billick, C.A. Garrison. California residential air exchange rates and residence volumes. *J Expo Anal Environ Epidemiol*; Vol 6(3):311-326.

This page intentionally left blank.

# Appendix C: Calculations for Development of Input Data Sets

## **GEOMET Technologies, Inc.**

20251 Century Boulevard • Germantown, MD 20874 • Telephone (301) 428-9898 • Telefax (301) 428-9482

#### MEMORANDUM

IE-4405

TO: Susan Lum

O GOGATI EGITT

FROM: Michael Koontz

DATE: October 23, 1995

SUBJECT: Calculations for Development of Input Data Sets

As you know, it was necessary for GEOMET to undertake a variety of data processing and calculation steps to develop some of the input data sets for the CPIEM software. The purpose of this memorandum is to document these steps, which are summarized below as they relate to indoor/outdoor concentrations, air exchange rates, volumes, and indoor sources.

#### Residential Indoor Concentrations

- For the 1984 TEAM study, the 1990 Woodland study, and the 1990 PTEAM study, the investigators reported the average concentration and the standard error for monitored VOCs (TEAM and Woodland) and PAHs (PTEAM). Because the model inputs require a mean and standard deviation, the standard deviation was obtained by multiplying the reported standard error by the square root of the reported sample size.
- For the 1987 TEAM study, 12-hour daytime and nighttime VOC samples were collected. The means and standard errors were reported for these data sets, but not for the 24-hour data. Consequently, files containing sampling results for each participating household were obtained through the EPA Environmental Monitoring Systems Laboratory in Las Vegas, and the daytime/nighttime values for each household were averaged to develop a 24-hour average from which the mean and standard deviation were computed. For consistency, the means and standard deviations for the 12-hour samples were also computed from this set of data.
- For the 1984-85 study of formaldehyde concentrations in conventional and mobile homes, conducted by the California Department of Health Services, the means and standard deviations were reported in a journal article along with histograms. Information was extracted from the histograms to summarize percentiles of the cumulative frequency

distribution for conventional homes during the winter and for mobile homes during the both the summer and the winter.

#### Concentrations for Travel in Vehicle

• Results were reported by the South Coast Air Quality Management District for a number of commuting trips during 1987-88 that averaged 33 minutes in duration. The results were reported on a volume/volume (parts per billion) basis. Because the model requires mass/volume (e.g., mg/m³ or µg/m³), the published results were converted using a formula based on the molecular weight of each compound.

#### **Outdoor Concentrations**

- For the 1984 TEAM study, the 1987 TEAM study, the 1990 Woodland study and the 1990 PTEAM study, the same processing and analysis steps were applied as described above for indoor concentrations.
- Data from the ARB air toxics monitoring network were acquired from ARB and processed and analyzed to developed distributional information (means and standard deviations) for selected VOCs (benzene, chloroform, formaldehyde, perchloroethylene, and trichloroethylene) and for benzo[a]pyrene. After eliminating sites with limited data, the records for each pollutant were statistically summarized across all monitoring sites. This procedure was followed for the state as a whole and for three regions (South Coast, San Francisco Bay area, and remainder of the state). A similar procedure was followed for inhalable particles (PM10) using a separate file obtained from ARB. The VOC results, reported in volume/volume units, were converted to mass/volume units using a formula based on the molecular weight of each compound.

#### Residential Air Exchange Rates

- For the 1987 TEAM study, air exchange rates measured during February and July were processed and summarized separately, using a database of PFT measurements developed by Versar and GEOMET for the U.S. Environmental Protection Agency. Air exchange rates for the 1984-85 study for SoCal Gas were also available in this database, but some errors were found in the portion of the database pertaining to this study; consequently, summaries reported by the investigators were used instead.
- For 1990 studies by ADM Associates and Berkeley Solar Group, the air exchange rates were not summarized by the investigators but the individual results were listed in their respective reports. The data listed in the reports were entered in a spreadsheet and then summarized statistically.

#### Residential Volumes

For the 1987 TEAM study, house volumes were summarized statistically using a database of PFT measurements developed by Versar and GEOMET for the U.S. Environmental Protection Agency. Volumes for the 1984-85 study for SoCal Gas were also in this database. The SoCal study had three measurement periods (March 1984, July 1984, and January 1985) for largely the same set of houses. Because the 1984 data were found to have some errors, the summary statistics on house volumes were calculated using the 1985 data.

 For the 1990 study by ADM Associates, house volumes were not summarized by the investigators but were listed in their report. The listed data were entered in a spreadsheet and the summarized statistically.

#### Residential Indoor Sources

- Inputs for chloroform on indoor water uses were developed from a report by the Metropolitan Water District of Southern California, which summarized daily uses per household for toilets, faucets, baths/showers, dishwashers and clothes washers. From these individual sources, total household water use per day was computed and used in developing model inputs reflecting all water uses combined.
- Inputs for benzo[a]pyrene were largely taken from the report on the 1990 PTEAM study.
  The investigators reported the average source strength but not the standard deviation.
  The standard deviation was estimated using limited statistics on percentiles reported by the investigators coupled with assumptions for the percentiles that were not reported.
- Inputs for nitrogen dioxide were based on unpublished data from the gas industry, obtained from the Gas Research Institute, on daily and hourly gas consumption by gas ranges, including pilot light consumption. The data were analyzed to separate the pilot light consumption from the remainder of range consumption (i.e., for cooking or for supplemental heating). Fuel consumption summary statistics initially were developed separately for breakfast, lunch and dinner. The fuel-consumption inputs were also used to develop inputs for duration of cooking for each meal. Subsequently, the three meals were combined to develop a single source for cooking; a Monte Carlo simulation was performed to develop an estimate of the standard deviation for duration of cooking for this combined source.

This page intentionally left blank.

## Appendix D: UNC User's Guide, Verification, and Validation

#### Introduction

UNC is a program developed for use with CPIEM to allow the user to conduct an uncertainty analysis for given CPIEM factors. For each CPIEM factor, the model inputs specify the distribution of that factor. Uncertainty analyses can be applied to CPIEM factors used for level 1-2, or for level 3, or both. The UNC program is in two parts. The first part of the program allows the user to define uncertainty distributions for their selected CPIEM inputs. UNC will randomly generate sets of CPIEM inputs for each factor by selecting values from the uncertainty distributions. The second part of the program reads in the output variability distributions from CPIEM and generates summary tables and graphs of the uncertainty of the variability distribution.

#### Installing and Uninstalling UNC

To install UNC, run the UNC\_setup.exe installation program. The default installation folder is "c:\Program Files\CPIEMunc" The folder "c:\Program Files\CPIEMunc\sampdata" contains example input files. To uninstall UNC, run the uninstall program uninstal exe found in the installation folder. When prompted, you can delete the additional data files in the installation folder that were created by UNC since the installation. Be sure to reboot your computer before reinstalling UNC.

The user can change from the default installation folder to another folder during installation. Afterwards, the user can change the file locations using the Defaults submenu of the Options menu. As discussed below, choosing this option brings up a screen where the user can tell the program what to use for the default locations for the initial directory, where the program expects to find data files, and the execution directory, where the program expects to find the executable files. The user can change the currently defined locations by left clicking on the box at the end of the directory location. This will bring up a new screen where the user can choose a particular drive and subdirectories as well as map onto a new network drive by left clicking on the box labeled NETWORK. Once the desired location has been selected the user must press the box labeled OK to return to the previous window. The user, however, should NOT change the default location of the executable files, unless ALL of the program files are moved.

#### **Files**

The three sampdata example input files example1.udt, example2.udt, and example3.udt show typical input formats for the four uncertainty types described below (continuous, discrete, default, case name). These examples are not intended to be realistic, but are instead provided to show how correctedly formatted inputs should appear. To examine and execute these examples, select an example file (Input Uncertainty Data menu, Select submenu), then select Modify from the Input Uncertainty Data menu and select the Define Factors button.

Using the UNC module to input uncertainty data will create a file with extension udt, e.g., test.udt. The user chooses the directory/folder using the Save As menu. When the test.udt file is executed (Execute menu), the program creates intermediate ASCII files test.int and test.dat and the output file test.out containing the uncertainty inputs for CPIEM (in the same folder as the test.udt file). Using the Calculate/View Statistics menu, the user gives the folder and name of a

concatenated CPIEM output statistics file with extension sta, e.g., all.sta. The program creates, in the same folder, a summary statistics file with extension ust (e.g., all.ust) and up to two gnuplot graph files with extensions plt (daily) and plth (hourly).

#### **Generate CPIEM Inputs**

For each CPIEM factor entered into the data set, the user may specify one of four options (continuous, case name, default, or discrete) for the uncertainty distribution of the parameters for the model input distributions (arithmetic lognormal (Ar. LN), exponential, geometric lognormal (Geo. LN), normal, or triangular). In this document and in the UNC software, the non-standard term "arithmetic lognormal" distribution defines a lognormal distribution where the given parameters are the (arithmetic) mean and standard deviation of the variable. The non-standard term "geometric lognormal" distribution defines a lognormal distribution where the given parameters are the geometric mean and geometric standard deviation of the variable. (By definition, the natural logarithms of the geometric mean and geometric standard deviation equal the mean and standard deviation of the natural logarithm of the variable.) The user then enters specific information for each of the uncertainty distributions requested.

The output of UNC is an ASCII file containing a matrix of X rows by N columns, where X is the number of CPIEM factors that the user entered into the input data file and N is the number of CPIEM simulations to be run. The values in the c<sup>th</sup> column are the randomly generated sets of values for each of the X CPIEM factors to be used in the c<sup>th</sup> simulation. For each input factor with a continuous, default, or discrete uncertainty distribution, the cell in row r and column c will contain the parameters for the distribution of the r<sup>th</sup> input factor for use in the c<sup>th</sup> simulation. For the case name uncertainty distribution, the cell in row r and column c will contain the case name of the distribution type selected for the r<sup>th</sup> input factor for use in the c<sup>th</sup> simulation.

For continuous uncertainty distributions, the user may choose between arithmetic lognormal (Ar. LN), geometric lognormal (Geo. LN), normal or uniform distributions for each parameter of the model input distribution. The user must then enter a mean or minimum and a standard deviation or maximum for each of the parameters for the uncertainty distribution. More specifically, the mean and standard deviation are entered for the normal and arithmetic lognormal distributions, the minimum and maximum are entered for the uniform distribution, and the geometric mean and geometric standard deviation are entered for the geometric lognormal distribution. The parameter may be set to be a constant (i.e., have no uncertainty) by selecting the uniform uncertainty distribution and setting the maximum equal to the minimum. A variant of Latin HyperSquare sampling is then used to derive an output data set for use with CPIEM. The Latin HyperSquare sampling used in UNC takes the uncertainty distributions defined by the user and divides each distribution into N slices, where N is the number of simulations set at the Execute stage. The user chooses either the midpoint or random point sampling method. For each distribution and slice, the UNC program then selects either the midpoint of the slice or a random number from the slice. This number is then randomly allocated to a simulation number in the output file.

For discrete uncertainty distributions, the user enters as many sets of parameters as desired with a minimum of two sets required. The data entry screen for the discrete distributions will tell the user which, and how many, numbers should be in each set (i.e., Amean,std;@ or Amin,mode,max;@). The UNC program then randomly allocates the specified parameter sets into N slots where N is the number of simulations set at the Execute stage. If the number of parameter sets is larger than N, the program randomly picks N parameters sets without replacement. If the number of parameter sets is smaller than N and there are P parameter sets,

the program will randomly pick, without replacement, from the parameter sets P times to fill the first P slots. The program then randomly picks again from the P parameter sets to fill the next set of P slots, and so on until all N slots have been filled.

For default uncertainty distributions, the user enters the parameters used to define the original model input distribution and enters a sample size S. The program then samples from the model input distribution S times, and computes new parameters for the model input distribution based on these S samples. The program repeats this process until all N slots, where N is the number of simulations set at the Execute stage, have been filled.

For case name uncertainty distributions, the user enters as many data set names ("case names") as desired, with a minimum of two names required. The UNC program then randomly allocates the specified case names into N slots where N is the number of simulations set at the Execute stage. If the number of case names is larger than N, the program randomly picks N case names without replacement. If the number of case names is smaller than N and there are D case names, the program will randomly pick, without replacement, from the case names D times to fill the first D slots. The program then randomly picks again from the D case names to fill the next set of D slots, and so on until all N slots have been filled. If the case name uncertainty distribution is selected, the user is still required to enter a statistical distribution for the model input (e.g., normal) although that information is ignored by UNC.

The defined uncertainty distributions for the continuous uncertainty type are truncated so that invalid values will not be generated. Invalid results for a continuous uncertainty distribution would be as follows:

- Mean for an exponential model input distribution that is less than or equal to zero.
- Standard deviation for a geometric lognormal model input distribution that is less than or equal to one, or a standard deviation for any other model input distribution that is less than or equal to zero.
- Mean for an arithmetic or geometric lognormal model input distribution that is less than or equal to zero.

A warning message will be printed out at the end of the output file describing the percentage of the uncertainty distribution that was truncated. If the parameters for triangular or uniform variability distributions for which a continuous uncertainty type has been specified are not in the correct order (e.g., minimum < mode < maximum), the program will set all parameter values to the minimum value (e.g., minimum = mode = maximum). The program will count the number of times this was done, and will print a message at the end of the output file to tell the user how many times this occurred.

The program will also check upon entry for valid values for the default and discrete uncertainty distributions. If an invalid value is entered, the user will get an error message at the time of entry stating the problem with the value so that a valid value may be entered.

Once all of the uncertainty distributions have been defined and the uncertainty input data set has been saved, the UNC program is executed and the resulting uncertainty data is output into a semicolon delimited ASCII file. The user may best view the output by importing the file into EXCEL, specifying that the columns are semicolon delimited, and then using EXCEL's Copy, Paste Special, and Transpose options under the Edit menu to reorganize the output. The user

then inputs this information into CPIEM and runs CPIEM N times, where N is the number of simulations.


Example UNC uncertainty input files are provided in the folder c:\Program Files\CPIEMunc\sampdata (assuming the default installation folders are used).

#### **Compute Summary Statistics and Graphs**

Once CPIEM has been run N times using the uncertainty inputs generated from UNC, the combined output files from CPIEM are read back into UNC so that basic statistics may be calculated and simple plots may be generated summarizing the uncertainty of the level 1-2 or level 3 output variability distributions.

Example UNC statistics input files are provided in the folder c:\Program Files\CPIEMunc\sampdata (assuming the default installation folders are used).

#### Main Menu



The Main Menu of UNC appears when the program is loaded. It contains the following pull down menus which can be accessed either by left clicking with the mouse on the desired menu, or by pressing the ALT key and then the key of the underlined letter in the name of the desired menu.

Input Uncertainty Data

**E**xecute


Calculate/View Statistics

**Options** 

### **Input Uncertainty Data**

The Input Uncertainty Data menu allows the user to create new files, select and load existing files, modify a loaded file, save a loaded file, or print a loaded file. The options are as follows and can be accessed either by left clicking with the mouse on the desired option, or by pressing the key of the underlined letter in the name of the desired option.

Se <u>L</u> ect	Selects an existing input data set.
<u>N</u> ew	Creates a new blank input data set.
<u>M</u> odify	Modifies the currently loaded input data set.
<u>S</u> ave	Saves the currently loaded input data set.
Save As	Saves the currently loaded input data set under a new name.
<u>P</u> rint	Creates a formatted and labeled version of the input data set and opens it using Notepad.



<u>Select</u>. Choosing this option brings up a standard Windows file selection window which lists all available files of the correct type in the current working directory. Files can be deleted, copied, renamed, zipped, etc. from this window.

New. Choosing this option brings up a window to begin creating a new data file. This will be discussed in more detail later.


<u>Print</u>. Choosing this option will create a formatted file, using Notepad, called Input.TXT that can be printed directly from Notepad, or can be saved for later access.

#### **Execute**

The Execute Menu contains only one item which can be accessed either by left clicking with the mouse on the option, or by pressing the key of the underlined letter in the name of the option. If the option is grayed, either an input file has not been loaded or a new input file has not been saved.

Create Uncertainty File

Creates an appropriate output uncertainty data set using the currently loaded input file.



#### Calculate/View Statistics


The Calculate/View Statistics Menu contains two items which can be accessed either by left clicking with the mouse on the desired option, or by pressing the key of the underlined letter in the name of the desired option.

Select CPIEM Uncertainty Output S

Selects an existing CPIEM output file.

Select Statistics File to View

Selects an existing output statistics file.




<u>Select CPIEM Uncertainty Output</u>. Choosing this option brings up a standard Windows file selection window which lists all available files of the correct type in the current working directory. Selection of a file causes the generation of the output statistics on the chosen CPIEM output file, brings up a window showing the generated output statistics, and offers the user an option of viewing a graph of the output statistics.

<u>Select Statistics File to View</u>. Choosing this option brings up a standard Windows file selection window which lists all available files of the correct type in the current working directory. Selection of a file opens a window showing the chosen file of output statistics and offers the user an option of viewing a graph of the output statistics.

## **Options**

The Options Menu contains three items which can be accessed either by left clicking with the mouse on the desired option, or by pressing the key of the underlined letter in the name of the desired option.

<u>E</u> xit	Can be used to Exit the UNC program.
<u>D</u> efaults	A pop up window is used to select the working directory for input data files and the working directory for output uncertainty data files.
<u>A</u> bout	Lists the version of the software along with contact information for technical support



<u>Defaults</u>. Choosing this option brings up a screen where the user can tell the program what to use for the default locations for the initial directory, where the program expects to find data files, and the execution directory, where the program expects to find the executable files. The user can change the currently defined locations by left clicking on the box at the end of the directory location. This will bring up a new screen where the user can choose a particular drive and subdirectories as well as map onto a new network drive by left clicking on the box labeled NETWORK. Once the desired location has been selected the user must press the box labeled OK to return to the previous window. The user, however, should NOT change the default location of the executable files, unless ALL of the program files are moved.

#### Status Bar

The Status Bar is located at the bottom of the Main Window in UNC. The first section lists text that tells the current status of the UNC program. The second section lists the currently loaded input file. If an input file is not loaded, the second section will contain the word None. If an input file has been loaded but has been modified and not yet saved, the name in the second section will appear in brackets.

## Navigating within Data Entry Screens

For the data entry screens, the user may use the TAB key to move to the next cell in each row, and may use the ENTER key to move to the next cell in each column if the cell does not have a drop down menu. The user may also navigate between cells by using the arrow keys. Drop down menus may be accessed by either left clicking on the arrow at the end of the box, or by hitting the ENTER key when in a cell with a drop down menu. To select a particular option in a drop down menu, left click on the desired choice, or press the ENTER key and then use the arrow keys until the desired choice is highlighted and then press the ENTER key again. If the

cell does not have a drop down menu, the user must press the ENTER key after entering information, or what was entered will NOT be saved upon moving to the next screen. If the cell background is highlighted, then the data entered in that cell has been saved and will not be lost upon moving to the next screen.

Right clicking on any cell in a screen brings up a menu to allow the user to cut or copy the cell contents and to paste to the selected cell what has been cut or copied from another cell.

#### **Default Filename Extensions**

By default, the UNC program expects files of certain types to have certain filename extensions. In some cases, the program will not recognize a file as being of the required type if it does not have the correct extension. For other file types, if the extension is not the default the program will not automatically find it, but it will open it without any problems. The default filename extensions are as follows:


- UDT Input data filename extension. UNC will not recognize files as input data files unless they have a filename extension of UDT.
- OUT Uncertainty output filename extension. If the file is renamed, an extension of OUT is not required.
- STA Compiled CPIEM output filename extension. UNC expects this file to have an extension of STA, but it is not required.
- UST Output statistics filename extension. If the file is renamed, an extension of UST is not required.
- PLT WGNUPLOT filename extension. If the file is renamed, an extension of PLT is not required.

## **Getting Started**

- Select an input uncertainty data set using the Input Uncertainty Data menu or select the New option under Input Uncertainty Data to enter data for a new data set. If a new data set is created, be sure to save the data set before moving on to the next step.
- Execute the program to generate the uncertainty data to be entered into CPIEM by choosing the Create Uncertainty File option under the Execute menu.
- Exit UNC and enter the output uncertainty data into CPIEM to get the necessary output files.
- Merge the multiple CPIEM output files into one large output file.
- Select a CPIEM output data set by choosing the Select CPIEM Uncertainty Output option under the Calculate/View Statistics menu to generate the statistics on the CPIEM output and to generate a graph of the output statistics.


### **Creating a New Input Data Set**

Selecting the option of New under the Input Uncertainty Data menu brings up the following screen:



The user will enter a title for the input data file that contains at most 80 characters, and the total number of CPIEM factors that are to be included in the uncertainty analysis. Once these fields have been completed, the user should left click on the button labeled ADefine Factors@.


This brings up another screen for entering specific data for each CPIEM factor.



The user should enter the name for each CPIEM factor in the first column (name can be no more than 10 characters) and the corresponding model input variability distribution in the second column. For the model input variability distributions, distributions must be entered from the pull down menu that is accessed by left clicking on the arrow at the end of the box or by pressing the ENTER key and using the arrow keys. Left clicking on the desired distribution in the menu or pressing the ENTER key when the desired distribution is highlighted selects that distribution to be inserted into the box. The user then must decide on an uncertainty distribution to be used, and must add this distribution in the third column. If the case name uncertainty distribution is selected, the selected variability distribution is ignored by UNC. The uncertainty distributions are entered in the same manner as the variability distributions. Only valid choices will appear in the drop down menus for each of the last two columns. Once all information has been entered, the user should left click on the button labeled AOK@ to proceed to the next screen. Left clicking on the button labeled ACANCEL@ at any time will return the user to the first screen in the input process.

The user may also add or delete a CPIEM factor on this screen. Right clicking on any cell in the screen brings up a menu to allow the user to add or delete a CPIEM factor to the list. A new line will appear at the bottom of the list if the ADD option is selected. If the DELETE option is selected, the row in which the cursor is currently will be deleted.

The next screen is for entering the distributions for parameters for the CPIEM factors for which a continuous uncertainty distribution was chosen.



Only those CPIEM factors for which a continuous uncertainty distribution was selected will appear on this screen, but each factor will appear on multiple lines: one for the mean, geometric mean or minimum of the model input variability distribution; one for the mode of the model input variability distribution if the distribution was triangular; and one for the standard deviation, geometric standard deviation, or maximum. For each parameter, the user should select an uncertainty distribution from the drop down menu which may be accessed by left clicking on the arrow at the end of the box or pressing ENTER and using the arrow keys. Only valid selections will appear in the drop down menu: uniform, normal, arithmetic lognormal, and geometric lognormal. Then, for each selected uncertainty distribution for each parameter, the user should enter a mean, geometric mean, or minimum for the corresponding distribution under the column AMean/Min@, and a standard deviation, geometric standard deviation, or maximum under the column AStd/Max@:

• Uniform: Mean/Min = minimum, Std/Max = maximum

Normal: Mean/Min = mean, Std/Max = standard deviation


Arithmetic Lognormal: Mean/Min = mean, Std/Max = standard deviation

Geometric Lognormal: Mean/Min = geom. mean, Std/Max = geom. standard deviation

The user may set a parameter to be a constant (no uncertainty) by selecting a uniform distribution and setting the maximum equal to the minimum. Once all columns have been

completed, the user should left click on the button labeled AOK@ to proceed to the next screen. If there were no CPIEM factors for which a continuous uncertainty distribution was selected, this screen will not appear.

The next screen is for entering the sets of parameters for the CPIEM factors for which a discrete uncertainty distribution was chosen.




Only those CPIEM factors for which a discrete uncertainty distribution was selected will appear on this screen. Each line will list a factor and the uncertainty distribution that was selected for the given factor. For each factor, the user should enter a set of parameters in the column ASets of Parameters@ with each parameter value in the list separated by a comma, and each set of parameters separated by a semicolon. The list of parameter sets must also end with a semicolon. The number and type of parameters the user should enter is indicated in the third column of the screen (i.e., Amean,std;@ indicates two values and Amin,mode,max;@ indicates three values). The user may enter as many sets of parameters as desired provided that at least two parameter sets are entered. If the user does not enter enough values, an error message will appear. The user must then press the ENTER key to save the entered list of parameters. Once this column has been completed, the user should left click on the button labeled AOK@ to proceed to the next screen. If there were no CPIEM factors for which a discrete uncertainty distribution was selected, this screen will not appear.

For each discrete uncertainty distribution, sets of parameter values may be repeated. This allows different sets to have different uncertainty probabilities. For example, for the triangular case, entering

1,2,3;1,2,3;2,4,5;

corresponds to assigning a 2/3 probability to the triangular distribution with min = 1, mode = 2, max = 3 and assigning a 1/3 probability to the triangular distribution with min = 2, mode = 4, max = 5. (1,2,3 was entered twice and 2,4,5 was entered once).

The next screen is for entering the parameters and sample size for the model input variability distributions for the CPIEM factors for which a default uncertainty distribution was chosen.




Only those model input variability distributions for CPIEM factors for which a default uncertainty distribution was selected will appear on this screen, but each model input variability distribution will appear on multiple lines: one for the mean, geometric mean, or minimum of the variability distribution; one for the mode of the variability distribution if the distribution was triangular; one for the standard deviation, geometric standard deviation, or maximum of the distribution; and one for the sample size. Under the column AParameter Value, @ the user should enter the value of the parameter indicated in the previous column: the mean, geometric mean, or minimum; the mode for triangular variability distributions; the standard deviation, geometric standard deviation, or the maximum; and the sample size. The sample size, S, defines how many times the user would like the UNC program to sample from the variability distribution.

For each simulation, the program will sample S times from the user-specified variability distribution and use those S values to compute a new set of parameter values. For example, for a uniform distribution with min=1, max=3, sample size=8, eight values will be selected randomly from the uniform distribution on the interval from 1 to 3 and the set of parameter values for the first CPIEM simulation will be the minimum and maximum of those eight values. Another set of eight values will be randomly selected to give the set of parameter values for the second simulation.

The user should press ENTER after entering values in each cell to ensure that the entered values are saved. Once the column has been completed, the user should left click on the button labeled AOK@ to proceed to the next screen. If there were no variability distributions for CPIEM factors for which a default uncertainty distribution was selected, this screen will not appear.

The next screen is for entering the data set names for the CPIEM factors for which a case name uncertainty distribution was chosen.



Only those CPIEM factors for which a case name uncertainty distribution was selected will appear on this screen. Each line will list a factor name and, for each factor, the user should enter a set of data set names (case names) in the second column with each name in the list separated by a semicolon. The list must also end with a semicolon. The user may enter as many data set names as desired as long as at least two data set names are entered. If the user does not enter enough names, an error message will appear. The user must then press the

ENTER key to save the entered list of names. Once this column has been completed, the user should left click on the button labeled AOK@ to proceed to the next screen. If there were no CPIEM factors for which a case name uncertainty distribution was selected, this screen will not appear.

For each case name uncertainty distribution, sets of case names may be repeated. This allows different distributions to have different uncertainty probabilities. For example, suppose the possible distributions for a given CPIEM factor have the case names NORMAL1, NORMAL2, and UNIFORM. Entering

#### NORMAL1; NORMAL2; NORMAL2; UNIFORM

corresponds to assigning a 1/4 probability to the NORMAL1 distribution, a 2/4=1/2 probability to the NORMAL2 distribution, and a 1/4 probability to the UNIFORM distribution.

Once all screens have been completed, the program will return to the initial input screen, and the user should left click on the button labeled AOK@. The user should then save the file by selecting the Input Uncertainty Data menu and the selecting the Save As option. A standard Windows file selection window will appear to allow the user to select the directory for which the data set should be saved. When entering the data set name, an extension need not be included since UNC will automatically select an extension of UDT. Files without an extension of UDT will not be recognized by UNC as input data files.

The user may then select the Create Uncertainty File option under the Execute menu to generate the uncertainty input data for use with CPIEM.


## Modifying an Input Data Set

To modify an input data set, the user must first load a data file by choosing the Select option under the Input Uncertainty Data menu. A standard Windows file selection window will appear to allow the user to find the desired subdirectory and data file. Once the user has selected an input data file, the screen will be blank, but the status bar will show that the file has been loaded and will show the name of the loaded file. The user should then choose the Modify option under the Input Uncertainty Data menu. This will bring up the initial input screen as though a new input data set were being created, except that the fields for title and total number of CPIEM factors are already completed. Title changes must be made here. Increases in the number of CPIEM factors may be made here or on the next screen, but decreases in the total number of CPIEM factors must be made on the next screen. The screens then proceed in the same manner as when creating new data sets. To change cell contents for which pull down menus are not available, click in the cell and type the new contents. The user must press ENTER after modifying cell contents without drop down menus to ensure that the information is saved.

## **Executing an Input Data Set**

To execute an input data set, the user must first have loaded a data file by choosing the Select option, and possibly the Modify option, under the Input Uncertainty Data menu. A standard Windows file selection window will appear to allow the user to find the desired subdirectory and data file. Once the user has selected an input data file, the screen will be blank, but the status bar will show that the file has been loaded and will show the name of the loaded file. The user should then choose the Create Uncertainty File option under the Execute menu. This will bring

up a window with two options for the user to select: to use the midpoint of each slice in the Latin HyperSquare calculations or to use a random point from each slice; and how many simulations should be run. To use the midpoint of each slice, the user should put a check in the box by left clicking on the center of the box. To use a random point, the user should make sure that the box is not checked. Use of the midpoint or a random point will only affect the calculations for those factors for which a continuous uncertainty distribution was defined. In general, the user is recommended to use the midpoint option when the number of simulations is low (e.g., less than 50). Using the midpoint option avoids unrepresentative simulations such that the low end, or high end, of each slice is always selected. Next, the user should enter the desired number of simulations.



The user may then execute the uncertainty data generation by left clicking on the OK button or may abort the process by left clicking on the CANCEL button. Once the program has completed the uncertainty data generation, the uncertainty output will appear in a new screen in Notepad. The uncertainty output file will automatically be given the same name as the uncertainty input file except with an extension of OUT. The file is automatically saved under this name, but the user may save the file under another name by selecting the Save As option under the File menu.

The user must then enter, by hand, the information from the uncertainty output file into CPIEM in order to obtain a CPIEM output file on which to generate statistics. The uncertainty output file is a semicolon delimited ASCII file. The user may best view the output by importing the file into EXCEL and specifying that the columns are semicolon delimited. Once the file has been imported, the user should use Excel's Copy, Paste Special, and Transpose options under the Edit menu to reorganize the output for easier interpretation.

If uncertainty distributions have not been specified for any level 3 CPIEM input factors, then an uncertainty analysis of the level 1-2 total indoor exposure concentration or dose is carried out by

running the CPIEM level 1-2 module N times, using each of the N sets of parameters generated by UNC. The N output distributions are combined, and the second part of the UNC program is used to generate the uncertainty distributions of the total indoor exposure concentration or dose, as discussed below.

If uncertainty distributions have been specified for some level 3 CPIEM factors, then the uncertainty analysis is carried out by running the CPIEM level 3 module followed by the CPIEM level 12 module N times. In the first set of simulations, the first set of level 3 input factors generated by UNC is used for the level 3 CPIEM module, and those level 3 outputs (i.e., hourly or daily indoor concentration distributions) are combined with the first set of level 1-2 input factors generated by UNC to provide inputs for the level 1-2 CPIEM module. The level 3 module may need to be run for several microenvironments. This whole process is repeated N times. The N level 1-2 output distributions are combined, and the second part of the UNC program is used to generate the uncertainty distributions of the total indoor exposure concentration or dose, as discussed below. If desired, the N level 3 output distributions can be combined, and the second part of the UNC program used to generate the uncertainty distributions of the hourly or daily average indoor concentrations.

After running CPIEM with the uncertainty output for the necessary number of times, the user must copy all of the level 12 CPIEM output files into one file, and, if level 3 uncertainty analyses are required, copy all of the level 3 CPIEM output files into another file. The easiest way to accomplish this is with the following DOS command:

#### copy \*.STE FILENAME.STA,

where \*.STE are the CPIEM output files and FILENAME.STA is the desired name of the new output file. The UNC program expects the extension of the compiled CPIEM output file to be STA.

The user may then choose the Select CPIEM Uncertainty Output option under the Calculate/View Statistics menu to generate the statistics on the CPIEM output.

## **Generate Statistics and Graph of CPIEM Output**

To generate statistics on the CPIEM output, the user must first select a CPIEM output file by choosing the Select CPIEM Uncertainty Output under the Calculate/View Statistics menu. Choosing this option brings up a standard Windows file selection window which lists all available files with an extension of STA in the current working directory. Only files with a STA extension may be used. Selection of a file causes the generation of the output statistics on the chosen CPIEM output file and brings up a window showing the generated output statistics in Notepad. The program generates the mean, standard deviation, median, minimum, maximum, and the 2.5th and 97.5th uncertainty percentiles for all of the statistics for either the TOTALS column from a level 1-2 analysis or the HOURLY and DAILY columns from a level 3 analysis. The program automatically detects the CPIEM level. The file of output statistics will automatically be given the same name as the CPIEM output file, except that the extension is changed to UST. The file is automatically saved under this name.

When the window of output statistics is closed, another window pops up asking if the user would like to view a graph of the output statistics. When the user chooses to view the graph of output statistics, a graph of the output statistics is generated using WGNUPLOT. This graph plots the median, 2.5th, and 97.5th percentiles of the output variability distribution, based on the

percentiles for each of the N uncertainty simulations. The median curve summarizes the output variability distribution (at the median level of uncertainty). The 2.5<sup>th</sup> and 95.5<sup>th</sup> curves provide a 95 % uncertainty envelope for the variability distribution. For a level 3, the user may choose to view either the daily or hourly average graphs or both. The file created for WGNUPLOT will be named the same as the statistics file except with an extension of PLT (for level 1-2 totals or level 3 daily averages) or PLTH (for level 3 hourly averages). These files can also be used directly with the WGNUPLOT program (WGNUPL32.EXE) to produce the graphs from outside the UNC program.

WGNUPLOT (Copyright 8 1986 - 1993, 1998, 1999 Thomas Williams, Colin Kelley and many others) is the graphing program used by UNC. UNC creates data files for WGNUPLOT.

Once the statistics have been generated, the user can view the statistics file and the corresponding graph by choosing the Select Statistics File to View under the Calculate/View Statistics menu. Choosing this option brings up a standard Windows file selection window which lists all available files with an extension of UST in the current working directory. Selection of a file opens that file in Notepad as was done when the statistics were calculated. After the Notepad window is closed, the user will again be offered the option of viewing graphs of the output statistics.

To copy the plot into Word or other Office products, right click on the graph, select "Copy to clipboard," open the Word document, and then use the paste command to copy from the clipboard into your document.

#### **Verification Tests**

The UNC module is used to analyze the sensitivity of the CPIEM output variability distributions to various parameters. UNC has two functions: (1) it provides an array of values with a certain distribution for a given parameter to be used as input to CPIEM; and (2) it summarizes the output from successive calculations (runs) of CPIEM into concise tables and charts. This greatly simplifies the assessment of the sensitivity. These two functions will be verified and discussed separately. Note that this test is a verification that the UNC code correctly makes calculations, rather than being a validation that the combined CPIEM and UNC modules correctly represent the uncertainty of real world indoor air exposures.

#### a. Generation of CPIEM Input Parameters

A calculation using CPIEM requires certain inputs. UNC generates distributions of input values that are suitable for analyzing, for example, the sensitivity of CPIEM to the precise value of these parameters. Suppose an input is the mean of an exponential distribution and we are interested in the effect of varying it according to different uncertainty distributions. UNC provides the choice of four different continuous distribution types for a CPIEM input parameter: (1) normal; (2) lognormal specifying arithmetic mean and standard deviation; (3) lognormal specifying geometric mean and standard deviation; and (4) uniform between two limits. The distributions for the possibilities (2) and (3) are equivalent but the different specifications are provided for convenience. The following test verifies the generation of data from these distributions.

Each input value for CPIEM will be designated for a simulation and UNC will generate a userspecified number, n, of these input values. The specified distribution of the parameter (in this example case the mean of exponential distribution) is divided into n slices of equal probability. A value for each slice is either taken as the probability midpoint, or as a random point in that slice interval. In the following we have made eight calculations with UNC to provide eight sets of 1000 potential values for the mean of the exponential distribution. Each of the distributions is requested twice, once with the slice midpoint and one with a random point in the slice.

The parameter distributions are straightforward and n=1000 values should accurately represent the profiles of the distributions. The theoretical frequency for any interval may be calculated and compared with the observed frequency using UNC.

i. Normal distribution with mean=6 and standard deviation=2 is specified. Since the simulated values are to be used as means for an exponential distribution, they must be positive and the normal curve is truncated at zero. This omits 0.135% of the true distribution and would correspond to one or two points out of 1000. This truncation effectively renormalizes the distribution so that the positive portion will have 100% and all the slices are moved upward slightly. The resulting curves are shown in Figures D-1 and D-2 along with tables showing the observed and theoretical frequencies of various bins. The bin label is the upper bound and the top bin contains all values greater than 12. There is essentially no difference between the theoretical and observed bin frequencies.

Bin	Frequency	Normal
0-1.5	11	10.87
1.5-3	55	54.58
3-4.5	160	159.82
4.5-6	273	273.37
6-7.5	274	273.37
7.5-9	160	159.82
9-10.5	55	54.58
10.5-12	11	10.87
over 12	1	1.35
Total	1 000	998 63




Figure D-1 Sample from Normal Distribution with Midpoint Slice Option

Bin	Frequency	Normal
0	11	10.87
1.5	55	54.58
3	160	159.82
4.5	273	273.37
6	274	273.37
7.5	160	159.82
9	55	54.58
10.5	11	10.87
12+	1	1.35
Total	1 000	998 63




Figure D-2 Sample from Normal Distribution with Random-Point Slice Option

- ii. Lognormal curve with arithmetic mean=4 and standard deviation=2. For a lognormal distribution, the logarithm of the variable has a normal distribution. Thus, the variable must be positive and there is no need to truncate the distribution. This also provides a simple way to evaluate the frequency profile by simply choosing the bin boundaries logarithmically so that the theoretical frequency distribution follows the normal, bell-shaped curve. For the arithmetic parameters given, the geometric mean is 4/sqrt(5/4)= 3.57771, and the logarithm of this is the mean of the logarithms of the variables. Thus, the logarithm of the geometric mean was chosen as one of the bin boundaries and the boundaries were set to vary by a factor of sqrt(2). The results for these calculations are shown in Figures D-3 and D-4. Again we see that there is essentially no difference between the theoretical and observed frequencies. Any difference may be due to roundoff or, in the case of the random midpoint option, sampling variability.
- iii. Lognormal curve with geometric mean=3.57771 and geometric standard deviation=1.60381. See Figures D-5 and D-6. An expression for the geometric mean from the arithmetic terms is given above. The geometric standard deviation, when the arithmetic mean is 4 and standard deviation is 2, is given by exp{sqrt[ln(5/4)]}= 1.60381, the value indicated. So, this is the same distribution as above (ii). Thus, we again chose the bin boundaries as above and we find essentially the same frequencies. The random point option for this distribution gives a perfectly symmetric distribution, like the theoretical. There is a random distribution of points near the bin boundaries, but the profile should be very close to the theoretical one, and sometimes exactly symmetric, as is here observed.
- iv. Uniform with minimum=1 and maximum=5. See Figures D-7 and D-8. This is an exceedingly simple distribution, but there is a slight difference in the two point choices. Presumably, one of the random point choices rounds to 1.4000 and is counted in the first bin. For the midpoint choice there is no problem. Each of the points is of the form 1.002+0.004(I-1), where I is an index between 1 and 1000. There is no point too near a boundary and each of the ten bins has an equal frequency of 100.

In summary, we have verified that UNC does accurately represent each of the selected distributions.

Bin	Frequency	LogNormal
	2	1.67
0.894427	12	12.20
1.264911	57	57.27
1.788854	160	160.43
2.529822	269	268.43
3.577709	268	268.43
5.059644	161	160.43
7.155418	57	57.27
10.11929	12	12.20
14.31084	2	1.67
Total	1,000	1,000




Figure D-3 Sample from Lognormal Distribution Specified with Arithmetic Mean and Standard Deviation, with Midpoint Slice Option

Bin	Frequency	LogNormal
	. 2	1.67
0.894427	12	12.20
1.264911	57	57.27
1.788854	160	160.43
2.529822	269	268.43
3.577709	268	268.43
5.059644	160	160.43
7.155418	58	57.27
10.11929	12	12.20
14.31084	2	1.67
Total	1,000	1,000




Figure D-4 Sample from Lognormal Distribution Specified with Arithmetic Mean and Standard Deviation, with Random-Point Slice Option

Bin	Frequency	LogNormal
	2	1.67
0.894427	12	12.20
1.264911	57	57.27
1.788854	160	160.43
2.529822	269	268.43
3.577709	268	268.43
5.059644	161	160.43
7.155418	57	57.27
10.11929	12	12.20
14.31084	2	1.67
Total	1,000	1,000




Figure D-5 Sample from Lognormal Distribution Specified with Geometric Mean and Standard Deviation, with Midpoint Slice Option

Bin	Frequency	LogNormal
	1	1.67
0.894427	13	12.20
1.264911	57	57.27
1.788854	161	160.43
2.529822	268	268.43
3.577709	268	268.43
5.059644	161	160.43
7.155418	57	57.27
10.11929	13	12.20
14.31084	1	1.67
Total	1,000	1,000




Figure D-6 Sample from Lognormal Distribution Specified with Geometric Mean and Standard Deviation, with Random-Point Slice Option

Bin	Frequency	Uniform
1.4	101	100
1.8	99	100
2.2	100	100
2.6	100	100
3.0	100	100
3.4	100	100
3.8	100	100
4.2	100	100
4.6	100	100
5.0	100	100
Total	1,000	1,000




Figure D-7 Sample from Uniform Distribution with Random-Point Slice Option

Bin	Frequency	Uniform
1.4	100	100
1.8	100	100
2.2	100	100
2.6	100	100
3.0	100	100
3.4	100	100
3.8	100	100
4.2	100	100
4.6	100	100
5.0	100	100
Total	1,000	1,000




Figure D-8 Sample from Uniform Distribution with Midpoint Slice Option

#### b. Using UNC to Summarize CPIEM Output

The second group of verification tests checks the combined operations of UNC and CPIEM. In each case, UNC is used to generate up to 20 sets of CPIEM input parameters, CPIEM generates output variability distributions based on these inputs, and then UNC generates the summary statistics and graphs of the uncertainty and variability. For this group of verification tests, the midpoint slice option for the LHS was used for each case.

For each of these calculations we consider hypothetical residential indoor concentrations and examine the variability distribution for the time-weighted daily average total exposure from the residential micro-environment only. For identification purposes only, the indoor pollutant is called formaldehyde. The inputs, however, do not necessarily correspond to formaldehyde data. For these tests a special version of CPIEM was used in which the weights for all activity patterns with any time spent in a non-residential microenvironment were reset to zero. Thus of the 2,962 activity patterns, 2,845 were given zero weight and the remaining 117 cases with all 24 hours spent in residence were given their original (positive) weights. In each CPIEM run, 5.000 trials were used, so that 5,000 activity patterns were selected at random with replacement. Of those 5,000, only those cases where the selected activity pattern was one of the 117 with all time spent in residence would be given a positive weight. (With significantly fewer than 5,000 trials there is a high probability that none of those 117 activity patterns will be selected, which will cause CPIEM to terminate abnormally because of a divide by zero error.) It follows that for this special version of CPIEM, the output variability distribution for each CPIEM run should match the selected input distribution if CPIEM is working correctly. More precisely, one should expect a good match but not an exact match since 5,000 trials were used instead of hypothetically infinitely many trials.

The calculations are divided into two sets: (1) the residential indoor concentration distribution is a lognormal distribution (CPIEM requires the arithmetic mean and standard deviation as parameters); and (2) the residential indoor concentration distribution is a mixture of normal distributions. The parameters of the distribution were assigned various uncertainty distributions using the UNC module. For each case in Set 1, the mean values of the mean and standard deviation parameters were 2 and 1, respectively. Thus for each case in Set 1 the output variability distribution at the median level of uncertainty should be approximately equal to a lognormal(2,1) distribution.

We shall first describe the various cases and present the graphical results (from UNC) in each case. Table D-1, described at the end of this section, compares the uncertainty/variability summary statistics from UNC with the values computed using statistical software.

i. Calculation Set 1, Case a: In these calculations no uncertainty was assigned to the lognormal mean and standard deviation parameters. Only the CPIEM random seed was allowed to vary across the 20 CPIEM runs. Thus the uncertainty for this case relates only to the variation of the random number seed and there should be little difference in the results. The results are shown in Figure D-9. As expected, the uncertainty of the variability distribution is small.




Figure D-9 Results for Set 1, Case a: Lognormal Distribution with No Parameter Uncertainty, Varying Random Seed

- ii. Calculation Set 1, Case b: In these calculations the CPIEM random number seed is constant across the 20 runs, and the parameter variation is from the default uncertainty distribution based on a sample size of 1000. With the random seed constant, CPIEM selects the same set of activity patterns in each run, although the simulated exposure distributions will vary. Because a large sample size was chosen for the default uncertainty distributions, there are only small variations in the input means and standard deviations. The uncertainty in the distribution is shown in Figure D-10.
- iii. Calculation Set 1, Case c: In these calculations the CPIEM random number seed is constant across the 20 runs, and the parameter variation is from the default uncertainty distribution based on a sample size of 10. Because a small sample size was chosen for the default uncertainty distributions, there are larger variations in the input means and standard deviations compared to case b. The uncertainty in the distribution is shown in Figure D-11. Both cases (b) and (c) appear quite similar; but note that the concentration variables are plotted on very different scales. There is significantly more variation in case (c) than in the first two cases, as expected.




Figure D-10 Results for Set 1, Case b: Lognormal Distribution with Default Paramet r Uncertainty, Uniform Random Seed, Sample Size = 1000




Figure D-11 Results for Set 1, Case c: Lognormal Distribution with Default Parameter Uncertainty, Uniform Random Seed, Sample Size = 10

- iv. Calculation Set 1, Case d: For these 20 calculations the mean of the distribution is uniformly distributed between 0 and 4 while the standard deviation is chosen from a normal distribution with mean value 1 and standard deviation 0.01. The distribution variation is shown in Figure D-12. The variation in the distributions is significantly wider than any of the first three sets of calculations. Note that there was one simulated exposure/concentration of 29.34 units, a very large value.
- v. Calculation Set 1, Case e: For these 20 calculations the mean of the distribution is requested to be uniformly distributed between –3 and 4, with the standard deviation having the same distribution as case (d). Since the mean parameter is the mean of a lognormal distribution, UNC chooses only positive values and, in fact, it chooses exactly the same 20 values as case (d). Since the standard deviation of the standard deviation is so small, 0.01, all the values for both these cases are essentially 1.0 and these two cases would have approximately the same inputs. If the numbers of UNC simulations and CPIEM trails had both been hypothetically infinite, then the output uncertainty/variability distributions for cases (d) and (e) should be identical. This result is verified in Figure D-13. Note however that different x scales were used. The second calculation has a maximum exposure of only 16.73, but the results for cases (d) and (e) are almost equivalent (much closer than they appear).
- vi. Calculation Set 1, Case f: For these 20 calculations the mean and standard deviations are taken from rather wide normal distributions, (2,1) and (1,0.5) respectively. The results for the variation in the distributions for these are shown in Figure D-14. As expected, the wide uncertainty distributions for the inputs lead to broad distributions for the resulting outputs. Both the mean and standard deviation for a lognormal distribution are positive values and

both these distributions are truncated appropriately by the UNC module. The mean of all the calculations is pushed a little above 2.0 (to 2.09) because of the truncation of the distribution of the mean parameter.




Figure D-12 Results for Set 1, Case d: Lognormal Distribution, with Mean Uniform (0,4), Standard Deviation Normal (1.0, 0.1)




Figure D-13 Results for Set 1, Case e: Lognormal Distribution with Mean Uniform (-3,4), Standard Deviation Normal (1, 0.1)




Figure D-14 Results for Set 1, Case f: Lognormal Distribution with Mean Normal (2,1),
Standard Deviation Normal (1, 0.5)

- Calculation Set 2, Case a: For these calculations, only four CPIEM runs are performed. vii. They are each normal distributions (with means of 4, 6, 8, and 10), each with a standard deviation of 1. This yields a wide variation in the distributions as shown in Figure D-15. The exposure distribution at the 97.5%-tile of uncertainty is equal to the exposure distribution at the 2.5%-tile plus 6 units. In fact, the detailed results of the individual calculations show that the percentiles for the mean 6 are 2 units above the percentiles for mean 4; the mean 8, 4 units above the mean 4; and the mean 10, 6 units above the percentiles for mean 4. This is the expected pattern because the four input distributions have almost identical shapes apart from their location parameters (which differ by multiples of 2). The four input distribution functions are not exactly parallel because of the truncation to positive concentration values, which has a small impact on the normal(4,1) case, but even smaller effects on the other three normal distributions. With the random point option for the LHS and/or using different random number seeds for each CPIEM run, the three curves in Figure D-15 would not appear so parallel. The expected output pattern (in the limiting case of infinitely many trials) for this normal mixture is a truncated normal(4,1) distribution at the 2.5 % uncertainty, a truncated normal(7,1) distribution at the 50 % uncertainty, and a truncated normal(8,1) distribution at the 97.5 % uncertainty. The simulation results match this pattern.
- viii. Calculation Set 2, Case b: For these calculations, 4 CPIEM runs with normal distributions are again performed. This time the first run has mean 4, and the next three all have mean equal 8; all have a standard deviation of 1. This case corresponds to a mixture of normal distributions where the normal(4,1) distribution has uncertainty weight 0.25 and the

normal(8,1) distribution has uncertainty weight 0.75. To allow some variation in the last three calculations (8,1), they were given different random number seeds. The results for this case are shown in Figure D-16. The 2.5%-tile is the same as the previous case. The median and 97.5%-tile are approximately equal, both being approximately 1 unit larger than the median curve in the previous case. The expected output pattern for this normal mixture is a truncated normal(4,1) distribution at the 2.5 % uncertainty, a truncated normal(8,1) distribution at the 50 % uncertainty, and a truncated normal(8,1) distribution at the 97.5 % uncertainty. (The median of 4, 8, 8, and 8 equals 8). The simulation results match this pattern.

ix. Calculation Set 2, Case c: For these calculations, 17 CPIEM runs with normal distributions are performed with means having values 3, 3.5, 4, ..., 11, each with standard deviation equal to 1. As in case a) of this set, all the simulations have the same random number seed, and the curves rise in parallel. The results are shown in Figure D-17. Here the median curve is about 4 units to the right of the 2.5%-tile line and 4 units to the left of the 97.5%-tile line. This is as expected because the median of the 17 mean values equals 7, the 2.5<sup>th</sup> percentile is 3, and the 97.5<sup>th</sup> percentile is 11.




Figure D-15 Results for Set 2, Case a: Four Normal Distributions of (4,1), (6,1), (8,1) and (10,1)




Figure D-16 Results for Set 2, Case b: Four Normal Distributions of (4,1), (8,1), (8,1) and (8,1)




Figure D-17 Results for Set 2, Case c: Seventeen Normal Distributions of (3,1), (3.5,1), (4,1), ......, (11,1)

Table D-1 contains the 2.5<sup>th</sup>, 50<sup>th</sup>, and 97.5<sup>th</sup> uncertainty percentiles for the arithmetic mean, 25<sup>th</sup>, 50<sup>th</sup>, and 75<sup>th</sup> percentiles of the variability distribution for each of the nine cases described above (corresponding to Figures D-9 to D-17). These uncertainty distributions are given in the columns headed "CPIEM Simulations." Also shown are the corresponding "exact" results based on a more extensive simulation using SAS statistical software-under the columns headed "SAS Simulations." For the SAS simulations in Set 1, 1000 vectors of uncertainty parameters were generated in each case (instead of 20), and each variability distribution was simulated 1,000 times. For the SAS simulations in Set 2, the number of uncertainty simulations was the same as for the CPIEM runs, but each variability distribution was simulated 1,000 times. (For the CPIEM runs, in effect only about 200 values were selected from each distribution because on the average about 95 % of the trials were given zero weight). The SAS results are much closer to the theoretical results corresponding to the limiting case of infinitely many simulations. The strong agreement between the SAS and CPIEM results confirms the model verification.

дрр пи	k D. ONC Oser s Gu	iue, verinicati ii, anu v	anuati ii.
4			
. •			

Set	Summary Statistic	SAS	simulation	s	CPE	ns	
		2.5 th	5 0 th	97.5th	2 .5 th	50 th	97.5th
1 a	M ean	1.94	2.00	2.07	1.84	2.00	2.16
1 a	25%	1.25	1.30	1.35	1 .2 1	1.30	1 .4 2
1 a	50%	1.73	1.79	1.85	1 .5 8	1.77	1.97
1 a	75%	2.37	2.46	2.56	2 .2 0	2.49	2.84
1 b	M ean	1.91	2.00	2.09	1.86	1.97	2.21
1 b	25%	1.23	1.30	1.38	1.16	1.29	1 .4 5
1 b	50%	1.70	1.79	1.88	1.66	1.77	1.98
1 b	75%	2.34	2.46	2.59	2.29	2.43	2.89
1 c	M ean	1.47	1.96	2.68	1.74	2.07.	2.57
lc	25%	0.95	1.33	1.85	1.08	1.41	1.66
1 c	50%	1.33	1.78	2 .3 8	1.61	1.89	2.32
lc	75%	1.76	2.38	3.33	2.15	2.59	3.28
1. d	M ean	0.11	2.04	3.90	0.10	2 .0 8	4.01
1 d	25%	0.00	1.34	3.18	0.00	1.35	3.26
1 d	50%	0.02	1.84	3.77	0.01	1.79	3 .8 0
1 d	75%	0.07	2.51	4.47	0.04	2.55	4.76
1 e	M ean	0.11	2.04	3.90	0.15	2.11	3.88
1 e	25%	0 .0 0	1.34	3 .1 8	0.00	1.41	3.13
1 e	50%	0.02	1.84	3.77	0.01	1.93	3.73
1 e	75%	0.07	2.51	4.47	0.06	2.63	4.59
1 f	M ean	0.35	2.02	4.00	0.31	2.01	4 .1 0
1 f	25%	0.05	1.31	3 4 6	0.04	1.22	3.23
1 f	50%	0.13	1.77	3.91	0.10	1.87	3.84
1 f	75%	0.36	2.43	4.60	0.35	2.66	4.95
2 a	M ean	4.01	7.07	10.01	3.91	6.91	9.91
2 a	25%	3.32	6.38	9.35	3.28	6.28	9.28
2 a	30%	4.02	7.08	10.01	3.89	6.89	9.89
2 a	75%	4 .6 9	7.76	10.64	4.59	7.59	10.59
2 b	M ean	4.00	7.98	8.04	3.91	7.90	7.97
2 b	25%	3 .3 8	7.30	7.31	3.28	7.23	7.32
2 b	50%	4.00	7.93	8.04	3.89	7.91	8.05
2 b	75%	4.65	8.66	8.73	4.59	8.57	8.59
2 C	M ean	3.02	6.98	11.02	2.91	6.96	11.02
2 C	25%	2.39	6.34	10.36	2.28	6.23	10.28
2 c	5 0 %	3.04	6.95	11.02	2.89	6.96	11.10
2 3	75%	3 .6 9	7 .6 9	11.73	3.59	7.56	11.66

**Table D-1 Uncertainty Distributions of Selected Summary Statistics** 

## **Validation Test**

A validation exercise was performed for the original version of CPIEM, using both the Level 1-2 and Level 3 modules, to simulate for daily average benzo(a)pyrene in Riverside residences and compared to values measured as part of the 1990 PTEAM study (Koontz et al. 1998). This validation exercise was repeated using the revised version of CPIEM and the UNC module to account for uncertainties in the model inputs. The findings showed that the PTEAM measurements were all within the CPIEM/UNC predicted uncertainty intervals except at the 90<sup>th</sup> percentile level.

Calculations were made of the distribution of indoor 24-hour concentrations for benzo(a)pyrene. A total of 20 different calculations were made involving a multi-dimensional matrix where 12 different parameters were varied. The development and rationale of the model was discussed in the Koontz report (Section 7.2.2). The starting values for the model parameters were given in Table 7-11 of the report and are reproduced here as Table D-2.

UNC used the default uncertainty option to calculate the matrix of input values. Thus from each input lognormal distribution, a sample was selected at random and the arithmetic mean and variance parameters were computed from the sample. In order for UNC to calculate default uncertainty distributions, the user must provide the size of the sample along with the parameters of the distribution for the input variables. For this analysis the assumed sample sizes were 100 for the indoor source emission rate, 36 for the ambient concentration, and 10 each for the airexchange rate and each of the contributing indoor volume distributions (3 of these). Apart from the ambient concentration distribution, these sample sizes are estimates, because the actual sample size values were not reported in Koontz et al. and the original PTEAM data were not readily available. No uncertainty was assumed for the number of indoor sources or for the penetration factor. There are 6 different lognormal distributions and UNC provided 20 sets of arithmetic means and standard deviations for each of these.

The mean of the summary statistics for the resulting distributions are similar to those found for the original CPIEM exercise (see Table D-3). The majority of the calculations gave very small concentrations (less than 1.0 ng/m³), but there are a few that have a relatively large magnitude concentration. For the 1000 trials each, the calculations gave maximum values that extended from 15 to 66 ng/m³. Figure 6-1, a plot obtained using UNC showing the uncertainty distribution for the daily concentration distribution, is dominated by this maximum value.

A numerical comparison of the summary statistics from the PTEAM study with the uncertainty intervals is also presented in Table D-3. Except for the 90<sup>th</sup> percentile and the standard deviation, all of the PTEAM summary statistics lie within the 95 % uncertainty interval from the 2.5<sup>th</sup> to the 97.5<sup>th</sup> uncertainty percentile.

The discrepancy at the upper end of the distribution may be the result of overestimating the unknown sample sizes for the emission rate, the air exchange rate, and/or the building volume inputs to UNC. If the sample sizes were assumed to be smaller, the uncertainty ranges would have been larger, and might have encompassed the measured value at the upper end of the distribution and the observed standard deviation. Another possible cause of the discrepancy is the assumption of no uncertainty for the penetration factor or the number of indoor sources. Accounting for uncertainty in either of these variables would also increase the uncertainty range, and possibly result in a wide enough range to encompass the measured data.

A third possibility is that the default uncertainty calculation underestimates the total uncertainty. As noted in section 4, the default uncertainty option accounts for uncertainty attributable to sampling variability only, i.e., uncertainty of the parameters for the distribution due to the fact that the specified distribution is based on observations of only a subset of the entire population of interest. Other types of uncertainty that would not be reflected in the default uncertainty distributions include uncertainty about the correct distributional form, uncertainty about the representativeness of the population from which the samples were taken (i.e., proper sampling frame), and uncertainty about the randomness of the sampling procedure. As is the case for any continuous distribution derived from relatively sparse data, the correct distributional forms of all the variables input to UNC are somewhat uncertain. In particular, Koontz et al. assumed that the emission source strength was lognormally distributed because comparison of the arithmetic mean and the range suggested a very skewed distribution. However, they did not have direct information about the standard deviation of the data set. Uncertainty about the distributional form of a highly skewed distribution is likely to be most influential at the upper end of the distribution, which is where our analysis showed a discrepancy. In addition for this analysis there is uncertainty about the sampling frame for the building volumes, since they were derived from studies other than the PTEAM study, from which the observed concentrations were taken.

Input Parameter	Distribution/Value
Percent of Residences with Indoor Sources	28
Number of Indoor Sources	Normal (1,0) <sup>a</sup>
Eṃission Rate, ng/h	Lognormal (390, 1285)
Outdoor Concentration, ng/m³	Lognormal (0.30, 0.36)
Penetration Factor	Normal (0.6, 0)
Indoor Sink, 1/h	Normal (0,0)
Indoor Volume, m <sup>3</sup>	
TEAM Study <sup>b</sup>	Lognormal (274.9, 110.6)
SoCal Study	Lognormal (309.5, 159.8)
ADM Study	Lognormal (354, 101)
Air Exchange Rate, 1/h	Lognormal (1.25, 1.02)

<sup>&</sup>lt;sup>a</sup> Values in parentheses are the mean and standard deviation of the distribution

Table D-2 Summary of Model Inputs for Benzo(a)pyrene (after Koontz et al. 1998, table 7-11)

<sup>&</sup>lt;sup>b</sup> Inputs for volume from three different studies in Southern California were equally weighted




Figure D-18 Plot generated by UNC that shows variation in the distribution calculated by CPIEM

	PTEAM	Original	riginal Uncertainty Distributions from CPIEM and UNC												
Statistic	Study	CPIEM <sup>a</sup>	Mean	Std Dev	Median	2.50%	97.50%	Minimum	Maximum						
Arith Mean	0.70	0.68	0.67	0.21	0.63	0.43	1.05	0.43	1.05						
Arith Std Dev	4.00	2.17	2.26	0.97	1.97	1.13	3.76	1.13	3.76						
Geo Mean			0.20	0.03	0.2	0.16	0.27	0.16	0.27						
Geo Std Dev			3.82	0.68	3.64	3.05	5.27	3.05	5.27						
Minimum		0.02	0.01	0.01 0.01 0.01		0.00	0.02	0.00	0.02						
Maximum		17.6	34.1	15.3	30.5	14.7	66.2	66.2 14.7							
5%			0.03	0.01	0.03	0.01	0.06	0.01	0.06						
10%	NQ⁵	0.04	0.04	0.01	0.04	0.02	0.08	0.02	0.08						
15%			0.06	0.02	0.05	0.03	0.09	0.03	0.09						
20%			0.07	0.02	0.06	0.04	0.10	0.04	0.10						
25%	0.08	0.08	0.08	0.02	0.07	0.05	0.12	0.05	0.12						
30%		·	0.09	0.02	0.09	0.07	0.13	0.07	0.13						
35%			0.11	0.02	0.11	0.09	0.15	0.09	. 0.15						
40%			0.13	0.02	0.13	0.10	0.18	0.10	0.18						
45%	·		0.15	0.02	0.15	0.12	0.20	0.12	0.20						
50%	0.19	0.15	0.17	0.02	0.17	0.13	0.22	0.13	0.22						
55%		-	0.20	0.03	0.20	0.16	0.25	0.16	0.25						
60%			0.23	0.03	0.23	0.18	0.28	0.18	0.28						
65%			0.27	0.04	0.27	0.21	0.34	0.21	0.34						
70%			0.33	0.06	0.33	0.25	0.44	0.25	0.44						
75%	0.36	0.36	0.42	0.08	0.41	0.29	0.55	0.29	0.55						
80%			0.54	0.13	0.53	0.35	0.76	0.35	0.76						
85%			0.78	0.22	0.74	0.49	1.25	0.49	1.25						
90%	0.65	1.15	1.25	0.4	1.15	0.74	2.02	0.74	2.02						
95%			2.51	0.95	2.16	1.42	4.58	1.42	4.58						
100%			34.14	15.25	30.53	14.74	66.21	14.74	66.21						

a Averages across 10 model runs with different random number seeds

b Not quantifiable

Table D-3 Model validation with CPIEM2.0 and UNC

## **Example**

In this section we shall present a simple example application using UNC applied to the same situation as used in the previous Validation section. One of the goals in providing this example is for the user to be able to check their model outputs against the Users Guide. Therefore, the default uncertainty simulations are not suitable for this example because the results depend upon the random seed that cannot be selected by the user for the UNC program. Instead, some reproducible results are developed using the continuous and case name uncertainty options.

in this example the UNC module is used to develop uncertainty estimates for the benzo(a)pyrene indoor concentrations using the same basic CPIEM inputs as in Table D-2 above. All the input distributions are assumed to be known except for the emission rate and indoor volume distributions.

For the emission rate, the distribution is assumed to be lognormal with an uncertain mean but a fixed standard deviation of 1285 ng/h. The mean parameter of the lognormal distribution is assumed to have an uncertainty distribution that is normal, with a mean of 390 ng/h and a standard deviation of 50 ng/h. Since UNC requires all rather than some of the distribution parameters to be assigned uncertainty distributions, the standard deviation parameter of the lognormal distribution is assigned an uncertainty distribution that is uniform, with a minimum of 1285 ng/h and a maximum of 1285 ng/h; this is equivalent to assuming a known value of 1285.

For the indoor volume, instead of giving equal weights to the TEAM, SoCAL, and ADM study lognormal distributions, the volume distribution is assumed to be uncertain so that the TEAM, SoCAL, and ADM distributions are regarded as being equally likely. The difference between these two approaches is that for the original analysis, with assigned weights, the three volume distributions are assumed to each apply to one third of California residences, whereas for this example analysis only one of the volume distributions applies to all California residences, but that selected distribution is equally likely to be from any of the three studies.

Figures D-19, D-20, D-21 and D-22 show how these uncertainty distributions are input to UNC. Figure D-19 shows the initial screen requesting two input factors with uncertainty. After pressing OK, the screen shown in Figure D-20 is to be filled in to specify that the emission factor has an arithmetic lognormal distribution with continuous uncertainty and the volume has case name uncertainty (the distribution for the volume is arbitrarily chosen to be arithmetic lognormal for this example although that information is not used by UNC). After completing the screen shown in Figure D-20 and pressing the OK button, the continuous uncertainty input screen will appear and should be filled out as in Figure D-21. The Figure D-21 inputs specify that the mean of the emission rate distribution is assumed to be normal, with mean = 390 and standard deviation = 50 and that the standard deviation of the emission rate distribution is uniform from 1285 to 1285. After completing the screen shown in Figure D-21 and pressing the OK button, the case name uncertainty input screen will appear and should be filled out as in Figure D-22, which assigns the three case name TEAM, SoCAL, and ADM equal probabilities. Finally, the user should press the OK button to reach a screen that again looks like Figure D-19, and then press the OK button to store the UNC inputs. The user should now use the Input Uncertainty Data menu Save As option to save this input file for future use under the name valid.udt.




Figure D-19 UNC Input Summary Screen for Benzo(a)pyrene Example




Figure D-20 UNC Uncertainty Distributions Summary Screen for Benzo(a)pyren Example




Figure D-21 UNC Continuous Uncertainty Distributions Screen for Benzo(a)pyren Example




Figure D-22 UNC Case Name Uncertainty Distributions Screen for Benzo(a)pyrene Example

The user can now execute the UNC model to create the uncertainty inputs for CPIEM. To do this, the Execute menu should be selected followed by the Create Uncertainty File submenu For this example, the user should request 6 simulations and should check the Use Midpoint option for the Latin Hypersquare sampling, as shown in Figure D-23.




Figure D-23 UNC Uncertainty Run Options Screen for Benzo(a)pyrene Example

After pressing the OK button, the UNC module computes the CPIEM uncertainty inputs and displays them as an ASCII file valid.out as shown in Figure D-24.

Parameter; Distribution; Sim 1; Sim 2; Sim 3; Sim 4; Sim 5; Sim 6;

Emissions; Ar.LN; (320.9,1285); (459.1,1285); (379.5,1285); (356.3,1285); (400.5,1285); (423.7,1285); The distribution for the mean parameter of the Ar.LN distribution for Cpiem Factor Emissions is poorly specified. The uncertainty distribution was truncated by 3.09535e-013% to avoid generation of impossible values.;

Volume; Case Name; (TEAM); (ADM); (SoCal); (ADM); (TEAM); (SoCal);

Note that the users' output file will almost certainly NOT look exactly like this because the randomly selected inputs will be rearranged.

## Figure D-24 UNC Output File Valid.Out for Benzo(a)pyrene Example

Since the random seed cannot be selected the user, the output file from running this application is unlikely to look exactly like Figure D-24. Instead the six pairs (320.9, 1285), (459.1, 1285), etc. will probably appear in a different order (the numbers will be the same because the Use Midpoint option was selected) and the six case names (TEAM), (ADM), etc. will probably appear in a different order.

Figure D-24 shows that for the first CPIEM simulation (Sim 1) the emission rate parameters are (320.9, 1285) and the volume distribution is from the TEAM study. For the second simulation, the emission rate parameters are (459.1, 1285) and the volume distribution is from the ADM study. And so on. It may be easier to display the CPIEM inputs by copying the valid.out file into Excel as a semicolon delimited file and then using the Copy and Paste Special, Transpose options to transpose the file. This produces the Excel file shown in Figure D-25 (the warning message row has been deleted).

Parameter Distribution	Emissions Ar.LN	Volume Case Name						
Sim 1	(320.9,1285)	(TEAM)						
Sim 2	(459.1,1285)	(ADM)						
Sim 3	(379.5,1285)	(SoCal)						
Sim-4	(356.3,1285)	(ADM)						
Sim 5	(400.5,1285)	(TEAM)						
∴ Sim 6	(423.7,1285)	(SoCal)						

Note that the users' output file will almost certainly NOT look exactly like this because the randomly selected inputs will be rearranged.

Figure D-25 Transposed UNC Output File Valid.xls for Benzo(a)pyrene Example

These 6 sets of inputs were then entered into the CPIEM model to give six simulations of 100 trials each using the CPIEM random seed 8740. The other factor inputs are exactly as in Table D-2, which corresponds to the CPIEM example "6.2.1" For example, for the first simulation, the CPIEM example 6.2.1 was modified so that the initial emission rate distribution had mean 320.9 instead of 390 (the standard deviation is unchanged) and so that the selected volume

distribution is from the TEAM study only (i.e., lognormal(274.9, 110.6)) and not an equally weighted mixture of the three studies. The output summary statistics file 6.2.1.stc was renamed as 6.2.1.1.sta. After the six CPIEM runs defined in Figure D-25 were completed, the six sta files were concatenated using the DOS command

## Copy \*.sta all.sta

Finally, the UNC module was rerun to generate the uncertainty distributions. The Calculate/View Statistics menu with the Select CPIEM Uncertainty Output submenu was used to select the all.sta concatenated statistics file that produced the output uncertainty summary table shown in Table D-4. For example, the arithmetic mean has an uncertainty interval from 0.53 to 0.68, with a mean value of 0.62.

Summary Statistics for: 6.2.1

Concentration
Average
Daily

Maximum		1.47	0.21	4.13	0.02	8.85	0.03	0.04	0.05	90.0	0.08	60.0	0.11	0.13	0.15	0.17	0.18	0.22	0.26	0.31	0.40	٠	ο.	1.58	3.83	8.85
Minium	2	٠	0.19	3.69	0	6.55	0.03	0.04	0.05	90.0	80.0		۲.		0.15	•	0.18	7	0.25	ε.	٣.	0.45	9.	٥.	2.82	٦.
97.5 %	ő	1.47	0.21	4.13	٥.	8.85	0.03	0.04	0.05	90.0	٥.	60.0	0.11	0.13	0.15	0.17	0.18	0.22	0.26	0.31	4.	0.53	9	Ŋ.	80	8.85
() () () () () () () () () () () () () (	0.53	•	0.19	٠	0.02	95.9	٥.	0.04	0.05	90.0	0.08	0.09	0.11	0.13	0.15	0.17	0.18	0.22	0.25	0.30	0.35	0.45	0.68	1.04	2.82	6.56
Median		1.30		3.98	٥.	7.95	۰.	0.04	٠	•	0.08	60.0	0.11	Τ.	۲.	۲.	۲.	•	ς.	ς.	ς.	0.49		1.40	3.53	7.95
Std Dev	0	0.13	0.01	0.17	0.00	0.85	0.00	0.00	٠	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.00	0.01	0.02	0.04	0.12	0.21	0.38	0.85
Mean	0.62	1.30	•	3.95	0.02	7.91	0.03	0.04	0.05	90.0	•	•	0.11	0.13	0.15	0.17	0.18	0.22	0.25	0.31	0.38	0.49	0.87	1.33	3.45	7.91
Statistic	Arith Mean	Arith Std Dev	Geo Mean	Geo Std Dev	Minimum	Maximum	₩ %	10%	15%	20%	25%	30%	35%	40%	45%	50%	55%	%09	65%	40%	75%	80%	85.0% 80%	806	95%	100%

Table D-4. Output Uncertainty Distributions from CPIEM and UNC for Benzo(a)pyrene Example.